SAP ABAP table RPM_TS_PROJECT_ARCH {RPM: Project data that can be changed externally}

RPM_TS_PROJECT_ARCH-APSTAT = RPM_PROJ_APST-APPST

RPM_PROJ_APST

MANDT [CLNT (3)]
APPST [NUMC (4)]

0..N

RPM_TS_PROJECT_ARCH-EXSTAT = RPM_PROJ_EXST-EXCST

RPM_PROJ_EXST

MANDT [CLNT (3)]
EXCST [NUMC (4)]

0..N

RPM_TS_PROJECT_ARCH-GEOGRAPHY = RPM_PROJ_GEOGR-GEOGRAPHY

RPM_PROJ_GEOGR

MANDT [CLNT (3)]
GEOGRAPHY [CHAR (4)]

0..N

RPM_PROJ_LOCAT

MANDT [CLNT (3)]
LOCATION [CHAR (4)]

RPM_TS_PROJECT_ARCH

SUBCATEGORY [NUMC (4)]
PHASE [NUMC (4)]
PTYPE [NUMC (4)]
TTYPE [NUMC (4)]
APSTAT [NUMC (4)]
EXSTAT [NUMC (4)]
CURRENCY [CUKY (5)]
LOCATION [CHAR (4)]
GEOGRAPHY [CHAR (4)]

1   1

1

RPM_TS_PROJECT_ARCH-LOCATION = RPM_PROJ_LOCAT-LOCATION

0..N

RPM_TS_PROJECT_ARCH-PHASE = RPM_PROJ_PHASE-PHASE

RPM_TS_PROJECT_ARCH-SUBCATEGORY = RPM_PROJ_SUBCAT-SUBCATEGORY

1
1
1

RPM_PROJ_PHASE

MANDT [CLNT (3)]
CATEGORY [NUMC (4)]
PHASE [NUMC (4)]

0..N

RPM_PROJ_SUBCAT

MANDT [CLNT (3)]
CATEGORY [NUMC (4)]
SUBCATEGORY [NUMC (4)]

1

RPM_TS_PROJECT_ARCH-TTYPE = RPM_PROJ_TTYPE-TTYPE

0..N

RPM_PROJ_TTYPE

MANDT [CLNT (3)]
CATEGORY [NUMC (4)]
TTYPE [NUMC (4)]

1   1

RPM_TS_PROJECT_ARCH-PTYPE = RPM_PROJ_TYPE-PTYPE

0..N

RPM_PROJ_TYPE

MANDT [CLNT (3)]
CATEGORY [NUMC (4)]
PTYPE [NUMC (4)]

RPM_TS_PROJECT_ARCH-CURRENCY = TCURC-WAERS

0..N

TCURC

MANDT [CLNT (3)]
WAERS [CUKY (5)]

0..N