

SAP ABAP table /BCV/C_DISPLAV {Display Values}

_BCV_C_DISPLAV	
<u>MANDT</u>	[CLNT (3)]
<u>QVIEW_ID</u>	[CHAR (32)]
<u>DISPLAY_ID</u>	[CHAR (16)]
<u>DISPLAY_ATTR</u>	[CHAR (10)]
<u>DISPLAY_ATTR_SEQ</u>	[NUMC (4)]
<u>QUERY_ID</u>	[CHAR (32)]
<u>ATTRIBUTE_ID</u>	[CHAR (30)]

_BCV_C_DISATTR	
<u>MANDT</u>	[CLNT (3)]
<u>DISPLAY_TYPE</u>	[CHAR (10)]
<u>DISPLAY_SUB_TYPE</u>	[CHAR (10)]
<u>DISPLAY_ATTR</u>	[CHAR (10)]

_BCV_C_DISPLAY	
<u>MANDT</u>	[CLNT (3)]
<u>QVIEW_ID</u>	[CHAR (32)]
<u>DISPLAY_ID</u>	[CHAR (16)]

_BCV_C_QRESA	
<u>MANDT</u>	[CLNT (3)]
<u>QUERY_ID</u>	[CHAR (32)]
<u>ATTRIBUTE_ID</u>	[CHAR (30)]

_BCV_C_QVIEWQA	
<u>MANDT</u>	[CLNT (3)]
<u>QVIEW_ID</u>	[CHAR (32)]
<u>QUERY_ID</u>	[CHAR (32)]

/BCV/C_DISPLAV-DISPLAY_ATTR = /BCV/C_DISATTR-DISPLAY_ATTR 0..N

1 /BCV/C_DISPLAV-DISPLAY_ID = /BCV/C_DISPLAY-DISPLAY_ID 0..N

1 /BCV/C_DISPLAV-QVIEW_ID = /BCV/C_DISPLAY-QVIEW_ID 0..N

1 /BCV/C_DISPLAV-ATTRIBUTE_ID = /BCV/C_QRESA-ATTRIBUTE_ID

1 /BCV/C_DISPLAV-QUERY_ID = /BCV/C_QVIEWQA-QUERY_ID 0..N

0..N