

SAP ABAP table /BEV3/CHBDKR {Print View CH}

/BEV3/CHBDKR-LCNUM = AKKP-LCNUM

| AKKP                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| LCNUM [CHAR (10)]       |

/BEV3/CHBDKR-EXNUM = EIKP-EXNUM

| EIKP                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| EXNUM [CHAR (10)]       |

/BEV3/CHBDKR-RPLNR = FPLA-FPLNR

| FPLA                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| FPLNR [CHAR (10)]       |

/BEV3/CHBDKR-J\_1AFITP = J\_1AFITP-J\_1AFITP

| J_1AFITP                |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| KOART [CHAR (1)]        |
| J_1AFITP [CHAR (2)]     |

/BEV3/CHBDKR-BUPLA = J\_1BBRANCH-BRANCH

| J_1BBRANCH              |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| BUKRS [CHAR (4)]        |
| BRANCH [CHAR (4)]       |

/BEV3/CHBDKR-KNKLI = KNA1-KUNNR

| KNA1                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| KUNNR [CHAR (10)]       |

/BEV3/CHBDKR-KUNAG = KNA1-KUNNR

| KONA                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| KNUMA [CHAR (10)]       |

/BEV3/CHBDKR-KUNRG = KNA1-KUNNR

/BEV3/CHBDKR-KNUMA = KONA-KNUMA

/BEV3/CHBDKR-MANDT = T000-MANDT

| T000                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |

/BEV3/CHBDKR-BUKRS = T001-BUKRS

| T001                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| BUKRS [CHAR (4)]        |

/BEV3/CHBDKR-LAND1 = T005-LAND1

| T005                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| LAND1 [CHAR (3)]        |

/BEV3/CHBDKR-COUNC = T005E-COUNC

| T005E                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| LAND1 [CHAR (3)]        |
| REGIO [CHAR (3)]        |
| COUNC [CHAR (3)]        |

/BEV3/CHBDKR-CITYC = T005G-CITYC

| T005G                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| LAND1 [CHAR (3)]        |
| REGIO [CHAR (3)]        |
| CITYC [CHAR (4)]        |

/BEV3/CHBDKR-REGIO = T005S-BLAND

| T005S                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| LAND1 [CHAR (3)]        |
| BLAND [CHAR (3)]        |

/BEV3/CHBDKR-KKBER = T014-KKBER

| T014                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| KKBER [CHAR (4)]        |

/BEV3/CHBDKR-MSCHL = T040-MSCHL

| T040                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| MSCHL [CHAR (1)]        |

/BEV3/CHBDKR-MANSP = T040S-MANSP

| T040S                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| MANSP [CHAR (1)]        |

/BEV3/CHBDKR-STGRD = T041C-STGRD

| T041C                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| STGRD [CHAR (2)]        |

/BEV3/CHBDKR-ZLSCH = T042Z-ZLSCH

| T042Z                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| LAND1 [CHAR (3)]        |
| ZLSCH [CHAR (1)]        |

/BEV3/CHBDKR-MABER = T047M-MABER

| T047M                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| BUKRS [CHAR (4)]        |
| MABER [CHAR (2)]        |

/BEV3/CHBDKR-KDGRP = T151-KDGRP

/BEV3/CHBDKR-BZIRK = T171-BZIRK

| T151                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| KDGRP [CHAR (2)]        |

/BEV3/CHBDKR-KONDA = T188-KONDA

| T171                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| BZIRK [CHAR (6)]        |

/BEV3/CHBDKR-PLTYP = T189-PLTYP

| T188                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| KONDA [CHAR (2)]        |

/BEV3/CHBDKR-KALSM = T683-KALSM

| T189                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| PLTYP [CHAR (2)]        |

/BEV3/CHBDKR-VBUND = T880-RCOMP

| T683                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| KVEWE [CHAR (1)]        |
| KAPPL [CHAR (2)]        |
| KALSM [CHAR (6)]        |

/BEV3/CHBDKR-AKWAE = TCURC-WAERS

/BEV3/CHBDKR-CMWAE = TCURC-WAERS

/BEV3/CHBDKR-STWAE = TCURC-WAERS

/BEV3/CHBDKR-WAERK = TCURC-WAERS

| T880                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| RCOMP [CHAR (6)]        |

| TCURC                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| WAERS [CUKY (5)]        |

/BEV3/CHBDKR-KURST = TCURV-KURST

| TCURV                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| KURST [CHAR (4)]        |

/BEV3/CHBDKR-HITYP\_PR = THIT-HITYP

| THIT                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| HITYP [CHAR (1)]        |

/BEV3/CHBDKR-INCO1 = TINC-INCO1

| TINC                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| INCO1 [CHAR (3)]        |

/BEV3/CHBDKR-SPART = TSPA-SPART

| TSPA                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| SPART [CHAR (2)]        |

/BEV3/CHBDKR-FKART = TVFK-FKART

| TVFK                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| FKART [CHAR (4)]        |

/BEV3/CHBDKR-FKART\_RL = TVFK-FKART

| TVKO                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| VKORG [CHAR (4)]        |

/BEV3/CHBDKR-KTGRD = TVKT-KTGRD

| TVKT                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| KTGRD [CHAR (2)]        |

/BEV3/CHBDKR-VSBED = TVSB-VSBED

| TVSB                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| VSBED [CHAR (2)]        |

/BEV3/CHBDKR-VTWEG = TVTW-VTWEG

| VTWV                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| VTWEG [CHAR (2)]        |

/BEV3/CHBDKR-SFAKN = VBUK-VBELN

| VBUK                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| VBELN [CHAR (10)]       |

/BEV3/CHBDKR-VBELN = VBUK-VBELN

/BEV3/CHBDKR

|                         |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| VBELN [CHAR (10)]       |
| FKART [CHAR (4)]        |
| WAERK [CUKY (5)]        |
| VKORG [CHAR (4)]        |
| VTWEG [CHAR (2)]        |
| KALSM [CHAR (6)]        |
| VSBED [CHAR (2)]        |
| KONDA [CHAR (2)]        |
| KDGRP [CHAR (2)]        |
| BZIRK [CHAR (6)]        |
| PLTYP [CHAR (2)]        |
| INCO1 [CHAR (3)]        |
| ZLSCH [CHAR (1)]        |
| KTGRD [CHAR (2)]        |
| LAND1 [CHAR (3)]        |
| REGIO [CHAR (3)]        |
| COUNC [CHAR (3)]        |
| CITYC [CHAR (4)]        |
| BUKRS [CHAR (4)]        |
| KUNRG [CHAR (10)]       |
| KUNAG [CHAR (10)]       |
| MABER [CHAR (2)]        |
| STWAE [CUKY (5)]        |
| EXNUM [CHAR (10)]       |
| SFAKN [CHAR (10)]       |
| KNUMA [CHAR (10)]       |
| FKART_RL [CHAR (4)]     |
| KURST [CHAR (4)]        |
| MSCHL [CHAR (1)]        |
| MANSP [CHAR (1)]        |
| SPART [CHAR (2)]        |
| KKBER [CHAR (4)]        |
| KNKLI [CHAR (10)]       |
| CMWAE [CUKY (5)]        |
| HITYP_PR [CHAR (1)]     |
| VBUND [CHAR (6)]        |
| RPLNR [CHAR (10)]       |
| LCNUM [CHAR (10)]       |
| J_1AFITP [CHAR (2)]     |
| AKWAE [CUKY (5)]        |
| BUPLA [CHAR (4)]        |
| STGRD [CHAR (2)]        |