

# SAP ABAP table /BEV3/CHRGBLST {Rule Performance Type}

| <b>_BEV3_CHRGBLST</b> |             |
|-----------------------|-------------|
| <u>MANDT</u>          | [CLNT (3)]  |
| <u>YVORGE</u>         | [NUMC (4)]  |
| <u>VWDART</u>         | [NUMC (4)]  |
| <u>VBKLASSE</u>       | [CHAR (4)]  |
| <u>RGIDENT</u>        | [NUMC (6)]  |
| <u>RGLATTR</u>        | [CHAR (30)] |
| <u>ZEITPKT</u>        | [NUMC (4)]  |
| <u>RGNUMMER</u>       | [NUMC (9)]  |
| <u>RGINSTANZ</u>      | [NUMC (9)]  |
| <u>BTRGLST</u>        | [CHAR (13)] |

/BEV3/CHRGBLST-BTRGLST = /BEV3/CHCL\_LSTK-BTRGLST 0..N

| <b>_BEV3_CHCL_LSTK</b> |             |
|------------------------|-------------|
| <u>MANDT</u>           | [CLNT (3)]  |
| <u>BTRGLST</u>         | [CHAR (13)] |

1 /BEV3/CHRGBLST-YVORGE = /BEV3/CHTBVORGE-YVORGE 0..N

| <b>_BEV3_CHTBVORGE</b> |            |
|------------------------|------------|
| <u>MANDT</u>           | [CLNT (3)] |
| <u>YVORGE</u>          | [NUMC (4)] |

1 /BEV3/CHRGBLST-VWDART = /BEV3/CHTVWDART-VWDART 1

| <b>_BEV3_CHTVWDART</b> |            |
|------------------------|------------|
| <u>MANDT</u>           | [CLNT (3)] |
| <u>YVORGE</u>          | [NUMC (4)] |
| <u>VWDART</u>          | [NUMC (4)] |

1 /BEV3/CHRGBLST-MANDT = T000-MANDT 0..N

| <b>T000</b>  |            |
|--------------|------------|
| <u>MANDT</u> | [CLNT (3)] |

0..N