

SAP ABAP table /SAPSRM/C_MDFSB {Meta Data Configuration for Set Fields}

/SAPSRM/C_MDFSB-ENABLED = /SAPSRM/C_FLG 2-XFIELD2

0..N

_SAPSRM_C_FLG_2
XFIELD2 [CHAR (1)]

/SAPSRM/C_MDFSB-REQUIRED = /SAPSRM/C_FLG 3-XFIELD3

0..N

_SAPSRM_C_FLG_3
XFIELD3 [CHAR (1)]

/SAPSRM/C_MDFSB-POSTEDITABLE = /SAPSRM/C_FLG 4-XFIELD4

0..N

_SAPSRM_C_FLG_4
XFIELD4 [CHAR (1)]

/SAPSRM/C_MDFSB-VISIBLE = /SAPSRM/C_FLG_D-XFIELD

0..N

_SAPSRM_C_FLG_D
XFIELD [CHAR (1)]

/SAPSRM/C_MDFSB-ENTRY_TYPE = /SAPSRM/C_MDFET-ENTRY_TYPE

0..N

_SAPSRM_C_MDFET
ENTRY_TYPE [CHAR (1)]

/SAPSRM/C_MDFSB-BUS_OBJ_TYPE = /SAPSRM/C_OBJTY-OBJECT_TYPE

0..N

_SAPSRM_C_OBJTY
OBJECT_TYPE [CHAR (10)]

/SAPSRM/C_MDFSB-SET_LEVEL = /SAPSRM/C_SETLV-SET_LEVEL

0..N

_SAPSRM_C_SETLV
SET_LEVEL [CHAR (6)]

/SAPSRM/C_MDFSB-SET_TYPE = /SAPSRM/C_SETTY-SET_TYPE

0..N

_SAPSRM_C_SETTY
SET_TYPE [CHAR (5)]
SET_TYPE_LONG [CHAR (20)]

/SAPSRM/C_MDFSB-FIELD_NAME = DD03L-FIELDNAME

0..N

DD03L
TABNAME [CHAR (30)]
FIELDNAME [CHAR (30)]
AS4LOCAL [CHAR (1)]
AS4VERS [NUMC (4)]
POSITION [NUMC (4)]

/SAPSRM/C_MDFSB-DYN_CONTROL_CLAS = SEOCCLASS-CLSNAME

0..N

SEOCCLASS
CLSNAME [CHAR (30)]

_SAPSRM_C_MDFSB
CLIENT [CLNT (3)]
SET_TYPE [CHAR (5)]
FIELD_NAME [CHAR (30)]
BUS_OBJ_TYPE [CHAR (10)]
SET_LEVEL [CHAR (6)]
SET_SUBTYPE [CHAR (32)]
ENTRY_TYPE [CHAR (1)]
VISIBLE [CHAR (1)]
ENABLED [CHAR (1)]
REQUIRED [CHAR (1)]
POSTEDITABLE [CHAR (1)]
DYN_CONTROL_CLAS [CHAR (30)]

{0,1}

{0,1}