

SAP ABAP table /SAPTRX/AOTYPES {Application object types}

/SAPTRX/AOTYPES-MAINDELTAB = /SAPTRX/AOALLTAB-TABLEDEF

/SAPTRX/AOTYPES-MAINOBJTAB = /SAPTRX/AOALLTAB-TABLEDEF

/SAPTRX/AOTYPES-MASTERREFTAB = /SAPTRX/AOALLTAB-TABLEDEF

/SAPTRX/AOTYPES-ALTTRKOBJTYPE = /SAPTRX/ASTOTYPE-TRK\_OBJ\_TYPE

/SAPTRX/AOTYPES-TRRELCOND = /SAPTRX/CONDID-COND\_ID

/SAPTRX/AOTYPES-BUSOBJFUNC = /SAPTRX/FUNCTION-FUNCTION\_ID

/SAPTRX/AOTYPES-CONTROLDATAFUNC = /SAPTRX/FUNCTION-FUNCTION\_ID

/SAPTRX/AOTYPES-EXPEVENTFUNC = /SAPTRX/FUNCTION-FUNCTION\_ID

/SAPTRX/AOTYPES-INFODATAFUNC = /SAPTRX/FUNCTION-FUNCTION\_ID

/SAPTRX/AOTYPES-REPOSTFUNC = /SAPTRX/FUNCTION-FUNCTION\_ID

/SAPTRX/AOTYPES-RETRIEVOBJFUNC = /SAPTRX/FUNCTION-FUNCTION\_ID

/SAPTRX/AOTYPES-TRKIDFUNC = /SAPTRX/FUNCTION-FUNCTION\_ID

/SAPTRX/AOTYPES-TRRELFUNC = /SAPTRX/FUNCTION-FUNCTION\_ID

/SAPTRX/AOTYPES-TRK\_OBJ\_TYPE = /SAPTRX/MTOTYPE-TRK\_OBJ\_TYPE

/SAPTRX/AOTYPES-TRXSERVERNAME = /SAPTRX/TRXSERV-TRX\_SERVER\_ID

/SAPTRX/AOTYPES-CLIENT = T000-MANDT

/SAPTRX/AOTYPES-BUSOBJTYPE = TOJTB-NAME

| _SAPTRX_AOALLTAB |             |
|------------------|-------------|
| TRK_OBJ_TYPE     | [CHAR (20)] |
| TABLEDEF         | [CHAR (30)] |

| _SAPTRX_ASTOTYPE |             |
|------------------|-------------|
| TRK_OBJ_TYPE     | [CHAR (20)] |

| _SAPTRX_CONDID |             |
|----------------|-------------|
| MANDT          | [CLNT (3)]  |
| COND_TYPE      | [CHAR (1)]  |
| COND_ID        | [CHAR (20)] |

| _SAPTRX_FUNCTION |             |
|------------------|-------------|
| MANDT            | [CLNT (3)]  |
| FUNC_TYPE        | [CHAR (1)]  |
| FUNCTION_ID      | [CHAR (20)] |

| _SAPTRX_MTOTYPE |             |
|-----------------|-------------|
| CLIENT          | [CLNT (3)]  |
| TRK_OBJ_TYPE    | [CHAR (20)] |

| _SAPTRX_TRXSERV |             |
|-----------------|-------------|
| TRX_SERVER_ID   | [CHAR (10)] |

| T000  |            |
|-------|------------|
| MANDT | [CLNT (3)] |

| TOJTB |             |
|-------|-------------|
| NAME  | [CHAR (10)] |

| _SAPTRX_AOTYPES |             |
|-----------------|-------------|
| CLIENT          | [CLNT (3)]  |
| TRK_OBJ_TYPE    | [CHAR (20)] |
| AOTYPE          | [CHAR (20)] |
| BUSOBJTYPE      | [CHAR (10)] |
| BUSOBJFUNC      | [CHAR (20)] |
| MAINOBJTAB      | [CHAR (30)] |
| MASTERREFTAB    | [CHAR (30)] |
| TRRELFUNC       | [CHAR (20)] |
| TRRELCOND       | [CHAR (20)] |
| TRKIDFUNC       | [CHAR (20)] |
| REPOSTFUNC      | [CHAR (20)] |
| CONTROLDATAFUNC | [CHAR (20)] |
| INFODATAFUNC    | [CHAR (20)] |
| RETRIEVOBJFUNC  | [CHAR (20)] |
| EXPEVENTFUNC    | [CHAR (20)] |
| TRXSERVERNAME   | [CHAR (10)] |
| MAINDELTAB      | [CHAR (30)] |
| ALTTRKOBJTYPE   | [CHAR (20)] |