

SAP ABAP table A459 {IS-M/SD: Employee Up-Front Commission}

A459
<u>MANDT</u> [CLNT (3)]
<u>KAPPL</u> [CHAR (2)]
<u>KSCHL</u> [CHAR (4)]
<u>VERSGE</u> [CHAR (10)]
<u>GPNR</u> [CHAR (10)]
<u>DRERZ</u> [CHAR (8)]
<u>MINBEZ</u> [NUMC (2)]
<u>MINEIN</u> [UNIT (3)]
<u>BZPERF</u> [CHAR (5)]
<u>KONDA</u> [CHAR (2)]
<u>DATBI</u> [DATS (8)]

JDTDRER
<u>MANDT</u> [CLNT (3)]
<u>DRERZ</u> [CHAR (8)]

JGTGPNR
<u>MANDT</u> [CLNT (3)]
<u>GPNR</u> [CHAR (10)]

T000
<u>MANDT</u> [CLNT (3)]

T006
<u>MANDT</u> [CLNT (3)]
<u>MSEHI</u> [UNIT (3)]

T188
<u>MANDT</u> [CLNT (3)]
<u>KONDA</u> [CHAR (2)]

T681A
<u>KAPPL</u> [CHAR (2)]

T685
<u>MANDT</u> [CLNT (3)]
<u>KVEWE</u> [CHAR (1)]
<u>KAPPL</u> [CHAR (2)]
<u>KSCHL</u> [CHAR (4)]

TJD09
<u>MANDT</u> [CLNT (3)]
<u>BEZPER</u> [CHAR (5)]

A459-DRERZ = JDTDRER-DRERZ

0..N

A459-GPNR = JGTGPNR-GPNR

0..N

A459-VERSGE = JGTGPNR-GPNR

0..N

A459-MANDT = T000-MANDT

0..N

A459-MINEIN = T006-MSEHI

0..N

A459-KONDA = T188-KONDA

0..N

A459-KAPPL = T681A-KAPPL

0..N

A459-KSCHL = T685-KSCHL

0..N

A459-BZPERF = TJD09-BEZPER

0..N