

SAP ABAP table AUFKV_REQ {Order for appropriation request}

AUFKV_REQ-ANFAUFNR = AUFK-AUFNR

AUFK
<u>MANDT</u> [CLNT (3)]
<u>AUFNR</u> [CHAR (12)]

AUFKV_REQ-REFNR = AUFK-AUFNR

CEPC
<u>MANDT</u> [CLNT (3)]
<u>PRCTR</u> [CHAR (10)]
<u>DATBI</u> [DATS (8)]
<u>KOKRS</u> [CHAR (4)]

AUFKV_REQ-KSTAR = CSKB-KSTAR

CSKB
<u>MANDT</u> [CLNT (3)]
<u>KOKRS</u> [CHAR (4)]
<u>KSTAR</u> [CHAR (10)]
<u>DATBI</u> [DATS (8)]

AUFKV_REQ-AKSTL = CSKS-KOSTL

CSKS
<u>MANDT</u> [CLNT (3)]
<u>KOKRS</u> [CHAR (4)]
<u>KOSTL</u> [CHAR (10)]
<u>DATBI</u> [DATS (8)]

AUFKV_REQ-CYCLE = CSKS-KOSTL

FERC_C7
<u>MANDT</u> [CLNT (3)]
<u>IND</u> [CHAR (4)]

AUFKV_REQ-KOSTL = CSKS-KOSTL

FERC_C7
<u>MANDT</u> [CLNT (3)]
<u>IND</u> [CHAR (4)]

AUFKV_REQ-KOSTV = CSKS-KOSTL

FERC_C7
<u>MANDT</u> [CLNT (3)]
<u>IND</u> [CHAR (4)]

AUFKV_REQ-FERC_IND = FERC_C7-IND

ONR00
<u>MANDT</u> [CLNT (3)]
<u>OBJNR</u> [CHAR (22)]

AUFKV_REQ-OBJNR = ONR00-OBJNR

PRPS
<u>MANDT</u> [CLNT (3)]
<u>PSPNR</u> [NUMC (8)]

AUFKV_REQ-PSPEL = PRPS-PSPNR

SKB1
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]
<u>SAKNR</u> [CHAR (10)]

AUFKV_REQ-SAKNR = SKB1-SAKNR

T000
<u>MANDT</u> [CLNT (3)]

AUFKV_REQ-MANDT = T000-MANDT

T000
<u>MANDT</u> [CLNT (3)]

AUFKV_REQ-ABUKR = T001-BUKRS

T001
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]

AUFKV_REQ-BUKRS = T001-BUKRS

T001
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]

AUFKV_REQ-SOWRK = T001W-WERKS

T001W
<u>MANDT</u> [CLNT (3)]
<u>WERKS</u> [CHAR (4)]

AUFKV_REQ-WERKS = T001W-WERKS

T001W
<u>MANDT</u> [CLNT (3)]
<u>WERKS</u> [CHAR (4)]

AUFKV_REQ-AUART = T003O-AUART

T003O
<u>CLIENT</u> [CLNT (3)]
<u>AUART</u> [CHAR (4)]

AUFKV_REQ-IZWEK = T087I-IZWEK

T087I
<u>MANDT</u> [CLNT (3)]
<u>IZWEK</u> [CHAR (2)]

AUFKV_REQ-UMWKZ = T087K-UMWKZ

T087K
<u>MANDT</u> [CLNT (3)]
<u>UMWKZ</u> [CHAR (5)]

AUFKV_REQ-STORT = T499S-STAND

T499S
<u>MANDT</u> [CLNT (3)]
<u>WERKS</u> [CHAR (4)]
<u>STAND</u> [CHAR (10)]

AUFKV_REQ-KAPPL = T681A-KAPPL

T681A
<u>KAPPL</u> [CHAR (2)]

AUFKV_REQ-KVEWE = T681V-KVEWE

T681V
<u>KVEWE</u> [CHAR (1)]

AUFKV_REQ-KALSM = T683-KALSM

T683
<u>MANDT</u> [CLNT (3)]
<u>KVEWE</u> [CHAR (1)]
<u>KAPPL</u> [CHAR (2)]
<u>KALSM</u> [CHAR (6)]

AUFKV_REQ-JV_JIBCL = T8J6A-CLASS

T8J6A
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]
<u>CLASS</u> [CHAR (3)]

AUFKV_REQ-JV_JIBSA = T8J6C-SUBCLASS

T8J6C
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]
<u>CLASS</u> [CHAR (3)]
<u>SUBCLASS</u> [CHAR (5)]

AUFKV_REQ-ETYPE = T8JG-ETYPE

T8JG
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]
<u>VNAME</u> [CHAR (6)]
<u>ETYPE</u> [CHAR (3)]
<u>EDATE</u> [NUMC (8)]

AUFKV_REQ-RECID = T8JJ-RECID

T8JJ
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]
<u>RECID</u> [CHAR (2)]

AUFKV_REQ-VNAME = T8JV-VNAME

T8JV
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]
<u>VNAME</u> [CHAR (6)]

AUFKV_REQ-SIZECL = TAIF5-SIZECL

TAIF5
<u>MANDT</u> [CLNT (3)]
<u>SIZECL</u> [CHAR (2)]

AUFKV_REQ-IVPRO = TAPRF-IVPRO

TAPRF
<u>MANDT</u> [CLNT (3)]
<u>IVPRO</u> [CHAR (6)]

AUFKV_REQ-LOGSYSTEM = TBDLS-LOGSYS

TBDLS
<u>LOGSYS</u> [CHAR (10)]

AUFKV_REQ-BEMOT = TBMOT-BEMOT

TBMOT
<u>MANDT</u> [CLNT (3)]
<u>BEMOT</u> [CHAR (2)]

AUFKV_REQ-WAERS = TCURC-WAERS

TCURC
<u>MANDT</u> [CLNT (3)]
<u>WAERS</u> [CUKY (5)]

AUFKV_REQ-FUNC_AREA = TFKB-FKBER

TFKB
<u>MANDT</u> [CLNT (3)]
<u>FKBER</u> [CHAR (16)]

AUFKV_REQ-GSBER = TGSB-GSBER

TGSB
<u>MANDT</u> [CLNT (3)]
<u>GSBER</u> [CHAR (4)]

AUFKV_REQ-KOKRS = TKA01-KOKRS

TKA01
<u>MANDT</u> [CLNT (3)]
<u>KOKRS</u> [CHAR (4)]

AUFKV_REQ-VOGRP = TKAVG-GRUPPE

TKAVG
<u>MANDT</u> [CLNT (3)]
<u>OBJID</u> [CHAR (1)]
<u>GRUPPE</u> [CHAR (4)]
<u>ACTIVITY</u> [CHAR (4)]

AUFKV_REQ-ABGSL = TKKAA-ABGSL

TKKAA
<u>MANDT</u> [CLNT (3)]
<u>ABGSL</u> [CHAR (6)]

AUFKV_REQ-ESTNR = TKO03-ASTNR

TKO03
<u>CLIENT</u> [CLNT (3)]
<u>ART</u> [CHAR (4)]
<u>ASTNR</u> [NUMC (2)]

AUFKV_REQ-ABKRS = TKO08-ABKRS

TKO08
<u>CLIENT</u> [CLNT (3)]
<u>KOKRS</u> [CHAR (4)]
<u>ABKRS</u> [NUMC (2)]

AUFKV_REQ-AWSLS = TKV01-AWSLS

TKV01
<u>MANDT</u> [CLNT (3)]
<u>AWOBA</u> [CHAR (2)]
<u>AWSLS</u> [CHAR (6)]

AUFKV_REQ-ZSCHM = TPI01-ZSCHM

TPI01
<u>MANDT</u> [CLNT (3)]
<u>ZSCHM</u> [CHAR (7)]

AUFKV_REQ-TXJCD = TTXJ-TXJCD

TTXJ
<u>MANDT</u> [CLNT (3)]
<u>KALSM</u> [CHAR (6)]
<u>TXJCD</u> [CHAR (15)]

AUFKV_REQ-VERAA_USER = USR02-BNAME

USR02
<u>MANDT</u> [CLNT (3)]
<u>BNAME</u> [CHAR (12)]

AUFKV_REQ-KDAUF = VBUK-VBELN

VBUK
<u>MANDT</u> [CLNT (3)]
<u>VBELN</u> [CHAR (10)]

AUFKV_REQ
<u>MANDT</u> [CLNT (3)]
<u>AUART</u> [CHAR (4)]
<u>REFNR</u> [CHAR (12)]
<u>WERKS</u> [CHAR (4)]
<u>GSBER</u> [CHAR (4)]
<u>KOKRS</u> [CHAR (4)]
<u>KOSTV</u> [CHAR (10)]
<u>STORT</u> [CHAR (10)]
<u>SOWRK</u> [CHAR (4)]
<u>WAERS</u> [CUKY (5)]
<u>ASTNR</u> [NUMC (2)]
<u>ESTNR</u> [NUMC (2)]
<u>VOGRP</u> [CHAR (4)]
<u>KVEWE</u> [CHAR (1)]
<u>KAPPL</u> [CHAR (2)]
<u>KALSM</u> [CHAR (6)]
<u>ABKRS</u> [NUMC (2)]
<u>KSTAR</u> [CHAR (10)]
<u>KOSTL</u> [CHAR (10)]
<u>SAKNR</u> [CHAR (10)]
<u>CYCLE</u> [CHAR (10)]
<u>SEQNR</u> [NUMC (4)]
<u>OBJNR</u> [CHAR (22)]
<u>PRCTR</u> [CHAR (10)]
<u>PSPEL</u> [NUMC (8)]
<u>AWSLS</u> [CHAR (6)]
<u>ABGSL</u> [CHAR (6)]
<u>TXJCD</u> [CHAR (15)]
<u>FUNC_AREA</u> [CHAR (16)]
<u>KDAUF</u> [CHAR (10)]
<u>IVPRO</u> [CHAR (6)]
<u>LOGSYSTEM</u> [CHAR (10)]
<u>ABUKR</u> [CHAR (4)]
<u>AKSTL</u> [CHAR (10)]
<u>SIZECL</u> [CHAR (2)]
<u>IZWEK</u> [CHAR (2)]
<u>UMWKZ</u> [CHAR (5)]
<u>ZSCHM</u> [CHAR (7)]
<u>ANFAUFNR</u> [CHAR (12)]
<u>BEMOT</u> [CHAR (2)]
<u>VERAA_USER</u> [CHAR (12)]
<u>VNAME</u> [CHAR (6)]
<u>RECID</u> [CHAR (2)]
<u>ETYPE</u> [CHAR (3)]
<u>JV_JIBCL</u> [CHAR (3)]
<u>JV_JIBSA</u> [CHAR (5)]
<u>FERC_IND</u> [CHAR (4)]