

SAP ABAP table BAPI\_RE\_RENTAL\_OBJECT\_DAT {Rental Obj. - Data}

| BAPI_RE_RENTAL_OBJECT_DAT                      |
|------------------------------------------------|
| <i>BUILDING_PART</i> [CHAR (2)]                |
| <i>FIXTURES_FITTINGS_CATEGORY</i> [CHAR (6)]   |
| <i>RSN_FOR_VARIANCE_IN_PERC_INC</i> [CHAR (2)] |
| <i>FLOOR</i> [NUMC (3)]                        |
| <i>LOCATION_ON_FLOOR</i> [CHAR (2)]            |
| <i>TOP_FLOOR</i> [NUMC (3)]                    |
| <i>STAT_PROF</i> [CHAR (8)]                    |

| TIV12                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>SGEBT</u> [CHAR (2)] |

| TIV37                     |
|---------------------------|
| <u>MANDT</u> [CLNT (3)]   |
| <u>SSTOCKW</u> [NUMC (3)] |

| TIV38                     |
|---------------------------|
| <u>MANDT</u> [CLNT (3)]   |
| <u>RLGESCH</u> [CHAR (2)] |

| TIV43                      |
|----------------------------|
| <u>MANDT</u> [CLNT (3)]    |
| <u>RPROZGRD</u> [CHAR (2)] |

| TIVAJRLRAFFCT                    |
|----------------------------------|
| <u>MANDT</u> [CLNT (3)]          |
| <u>RLRA</u> [CHAR (6)]           |
| <u>RLRAFIXFITCATE</u> [CHAR (6)] |

| TJ20                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>STSMA</u> [CHAR (8)] |

BAPI\_RE\_RENTAL\_OBJECT\_DAT-BUILDING\_PART = TIV12-SGEBT

0..N

{0,1}

BAPI\_RE\_RENTAL\_OBJECT\_DAT-FLOOR = TIV37-SSTOCKW

0..N

{0,1}

BAPI\_RE\_RENTAL\_OBJECT\_DAT-TOP\_FLOOR = TIV37-SSTOCKW

0..N

{0,1}

BAPI\_RE\_RENTAL\_OBJECT\_DAT-LOCATION\_ON\_FLOOR = TIV38-RLGESCH

0..N

{0,1}

BAPI\_RE\_RENTAL\_OBJECT\_DAT-RSN\_FOR\_VARIANCE\_IN\_PERC\_INC = TIV43-RPROZGRD

{0,1}

BAPI\_RE\_RENTAL\_OBJECT\_DAT-FIXTURES\_FITTINGS\_CATEGORY = TIVAJRLRAFFCT-RLRAFIXFITCATE

0..N

{0,1}

BAPI\_RE\_RENTAL\_OBJECT\_DAT-STAT\_PROF = TJ20-STSMA

0..N

0..N