

SAP ABAP table CE0S_GO {Quickstart Template}

CE0S_GO
<u>MANDT</u> [CLNT (3)]
<u>PALEDGER</u> [CHAR (2)]
<u>VRGAR</u> [CHAR (1)]
<u>VERSI</u> [CHAR (3)]
<u>PERIQ</u> [NUMC (7)]
<u>PAOBJNR</u> [NUMC (10)]
<u>PASUBNR</u> [NUMC (4)]
<u>BELNR</u> [CHAR (10)]
<u>POSNR</u> [CHAR (6)]
<u>KNDNR</u> [CHAR (10)]
<u>ARTNR</u> [CHAR (18)]
<u>FKART</u> [CHAR (4)]
<u>FRWAE</u> [CUKY (5)]
<u>REC_WAERS</u> [CUKY (5)]
<u>KAUFN</u> [CHAR (10)]
<u>RKAUFNR</u> [CHAR (12)]
<u>SKOST</u> [CHAR (10)]
<u>PRZNR</u> [CHAR (12)]
<u>BUKRS</u> [CHAR (4)]
<u>KOKRS</u> [CHAR (4)]
<u>WERKS</u> [CHAR (4)]
<u>GSBER</u> [CHAR (4)]
<u>VKORG</u> [CHAR (4)]
<u>VTWEG</u> [CHAR (2)]
<u>SPART</u> [CHAR (2)]
<u>KSTAR</u> [CHAR (10)]
<u>PSPNR</u> [NUMC (8)]
<u>KSTRG</u> [CHAR (12)]
<u>PRCTR</u> [CHAR (10)]
<u>PPRCTR</u> [CHAR (10)]
<u>COPA_AWSYS</u> [CHAR (10)]
<u>MEINH</u> [UNIT (3)]
<u>LSTAR</u> [CHAR (6)]
<u>BRSCH</u> [CHAR (4)]
<u>BZIRK</u> [CHAR (6)]
<u>KDGRP</u> [CHAR (2)]
<u>KMVKBU</u> [CHAR (4)]
<u>MATKL</u> [CHAR (9)]
<u>VKGRP</u> [CHAR (3)]
<u>KMWNHG</u> [NUMC (2)]
<u>KWSVME_ME</u> [UNIT (3)]

CE0S_GO-RKAUFNR = AUFK-AUFNR

0..N

AUFK
<u>MANDT</u> [CLNT (3)]
<u>AUFNR</u> [CHAR (12)]

CE0S_GO-PRZNR = CBPR-PRZNR

0..N

CBPR
<u>MANDT</u> [CLNT (3)]
<u>KOKRS</u> [CHAR (4)]
<u>PRZNR</u> [CHAR (12)]
<u>DATBI</u> [DATS (8)]

CE0S_GO-PPRCTR = CEPC-PRCTR

0..N

CEPC
<u>MANDT</u> [CLNT (3)]
<u>PRCTR</u> [CHAR (10)]
<u>DATBI</u> [DATS (8)]
<u>KOKRS</u> [CHAR (4)]

CE0S_GO-PRCTR = CEPC-PRCTR

0..N

CKPH
<u>MANDT</u> [CLNT (3)]
<u>KSTRG</u> [CHAR (12)]
<u>DATBI</u> [DATS (8)]

CE0S_GO-KSTRG = CKPH-KSTRG

0..N

CSKA
<u>MANDT</u> [CLNT (3)]
<u>KTOPL</u> [CHAR (4)]
<u>KSTAR</u> [CHAR (10)]

CE0S_GO-KSTAR = CSKA-KSTAR

0..N

CSKS
<u>MANDT</u> [CLNT (3)]
<u>KOKRS</u> [CHAR (4)]
<u>KOSTL</u> [CHAR (10)]
<u>DATBI</u> [DATS (8)]

CE0S_GO-SKOST = CSKS-KOSTL

0..N

CSLA
<u>MANDT</u> [CLNT (3)]
<u>KOKRS</u> [CHAR (4)]
<u>LSTAR</u> [CHAR (6)]
<u>DATBI</u> [DATS (8)]

CE0S_GO-LSTAR = CSLA-LSTAR

0..N

KNA1
<u>MANDT</u> [CLNT (3)]
<u>KUNNR</u> [CHAR (10)]

CE0S_GO-KNDNR = KNA1-KUNNR

0..N

MARA
<u>MANDT</u> [CLNT (3)]
<u>MATNR</u> [CHAR (18)]

CE0S_GO-ARTNR = MARA-MATNR

0..N

PRPS
<u>MANDT</u> [CLNT (3)]
<u>PSPNR</u> [NUMC (8)]

CE0S_GO-PSPNR = PRPS-PSPNR

0..N

T000
<u>MANDT</u> [CLNT (3)]

CE0S_GO-MANDT = T000-MANDT

0..N

T001
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]

CE0S_GO-BUKRS = T001-BUKRS

0..N

T001W
<u>MANDT</u> [CLNT (3)]
<u>WERKS</u> [CHAR (4)]

CE0S_GO-WERKS = T001W-WERKS

0..N

T006
<u>MANDT</u> [CLNT (3)]
<u>MSEHI</u> [UNIT (3)]

CE0S_GO-KWSVME_ME = T006-MSEHI

0..N

T016
<u>MANDT</u> [CLNT (3)]
<u>BRSCH</u> [CHAR (4)]

CE0S_GO-MEINH = T006-MSEHI

0..N

T016
<u>MANDT</u> [CLNT (3)]
<u>BRSCH</u> [CHAR (4)]

CE0S_GO-BRSCH = T016-BRSCH

0..N

T023
<u>MANDT</u> [CLNT (3)]
<u>MATKL</u> [CHAR (9)]

CE0S_GO-MATKL = T023-MATKL

0..N

T151
<u>MANDT</u> [CLNT (3)]
<u>KDGRP</u> [CHAR (2)]

CE0S_GO-KDGRP = T151-KDGRP

0..N

T171
<u>MANDT</u> [CLNT (3)]
<u>BZIRK</u> [CHAR (6)]

CE0S_GO-BZIRK = T171-BZIRK

0..N

T2246
<u>MANDT</u> [CLNT (3)]
<u>KMWNHG</u> [NUMC (2)]

CE0S_GO-KMWNHG = T2246-KMWNHG

0..N

T2246
<u>MANDT</u> [CLNT (3)]
<u>KMWNHG</u> [NUMC (2)]

CE0S_GO-COPA_AWSYS = TBDLS-LOGSYS

0..N

TBDLS
<u>LOGSYS</u> [CHAR (10)]

CE0S_GO-LOGSYS = TBDLS-LOGSYS

0..N

TCURC
<u>MANDT</u> [CLNT (3)]
<u>WAERS</u> [CUKY (5)]

CE0S_GO-TCURC = TCURC-WAERS

0..N

TGSB
<u>MANDT</u> [CLNT (3)]
<u>GSBER</u> [CHAR (4)]

CE0S_GO-GSBER = TGSB-GSBER

0..N

TKA01
<u>MANDT</u> [CLNT (3)]
<u>KOKRS</u> [CHAR (4)]

CE0S_GO-KOKRS = TKA01-KOKRS

0..N

TKEL
<u>MANDT</u> [CLNT (3)]
<u>PALEDGER</u> [CHAR (2)]

CE0S_GO-PALEDGER = TKEL-PALEDGER

0..N

TKVS
<u>MANDT</u> [CLNT (3)]
<u>VERSI</u> [CHAR (3)]

CE0S_GO-VERSI = TKVS-VERSI

0..N

TSPA
<u>MANDT</u> [CLNT (3)]
<u>SPART</u> [CHAR (2)]

CE0S_GO-SPART = TSPA-SPART

0..N

TVBUR
<u>MANDT</u> [CLNT (3)]
<u>VKBUR</u> [CHAR (4)]

CE0S_GO-KMVKBU = TVBUR-VKBUR

0..N

TVFK
<u>MANDT</u> [CLNT (3)]
<u>FKART</u> [CHAR (4)]

CE0S_GO-FKART = TVFK-FKART

0..N

TVGA
<u>MANDT</u> [CLNT (3)]
<u>VRGAR</u> [CHAR (1)]

CE0S_GO-VRGAR = TVGA-VRGAR

0..N

TVKGR
<u>MANDT</u> [CLNT (3)]
<u>VKGRP</u> [CHAR (3)]

CE0S_GO-VKGRP = TVKGR-VKGRP

0..N

TVKO
<u>MANDT</u> [CLNT (3)]
<u>VKORG</u> [CHAR (4)]

CE0S_GO-VKORG = TVKO-VKORG

0..N

TVTW
<u>MANDT</u> [CLNT (3)]
<u>VTWEG</u> [CHAR (2)]

CE0S_GO-VTWEG = TVTW-VTWEG

0..N

VBUK
<u>MANDT</u> [CLNT (3)]
<u>VBELN</u> [CHAR (10)]

CE0S_GO-KAUFN = VBUK-VBELN

0..N