

SAP ABAP table CMIG_OTYPES {Customizing - iPPE Migration: Object Types}

CMIG_OTYPES-PVS_ALT_HDN = CPATYPE-PATYPE

0..N

0..N

CPATYPE	
<u>MANDT</u>	[CLNT (3)]
<u>PATYPE</u>	[CHAR (8)]

CMIG_OTYPES-VAS_ALT_HD = CPATYPE-PATYPE

0..N

CMIG_OTYPES-PVS_NODE_HD = CPNTYPE-PNTYPE

0..N

0..N

0..N

0..N

CPNTYPE	
<u>MANDT</u>	[CLNT (3)]
<u>PNTYPE</u>	[CHAR (8)]

CMIG_OTYPES-PVS_NODE_ST = CPNTYPE-PNTYPE

CMIG_OTYPES-VAS_NODE_HD = CPNTYPE-PNTYPE

0..N

0..N

0..N

CMIG_OTYPES-PVS_REL = CPRTYPE-PRTYPE

CMIG_OTYPES-VAS_REL = CPRTYPE-PRTYPE

0..N

0..N

CPRTYPE	
<u>MANDT</u>	[CLNT (3)]
<u>PRTYPE</u>	[CHAR (8)]
<u>CPRCNT</u>	[NUMC (8)]

CMIG_OTYPES-PVS_VAR_HD = CPVTYPE-PVTYPE

0..N

CMIG_OTYPES-PVS_VAR_ST = CPVTYPE-PVTYPE

0..N

0..N

0..N

0..N

0..N

0..N

CPVTYPE	
<u>MANDT</u>	[CLNT (3)]
<u>PVTYPE</u>	[CHAR (8)]

CMIG_OTYPES-VAS_VAR_HD = CPVTYPE-PVTYPE

CMIG_OTYPES-VAS_VAR_ST = CPVTYPE-PVTYPE

0..N

CMIG_OTYPES	
<u>MANDT</u>	[CLNT (3)]
<u>VAS_NODE_HD</u>	[CHAR (8)]
<u>VAS_VAR_HD</u>	[CHAR (8)]
<u>VAS_ALT_HD</u>	[CHAR (8)]
<u>VAS_VAR_ST</u>	[CHAR (8)]
<u>VAS_REL</u>	[CHAR (8)]
<u>PVS_NODE_HD</u>	[CHAR (8)]
<u>PVS_VAR_HD</u>	[CHAR (8)]
<u>PVS_VAR_ST</u>	[CHAR (8)]
<u>PVS_NODE_ST</u>	[CHAR (8)]
<u>PVS_ALT_HDN</u>	[CHAR (8)]
<u>PVS_REL</u>	[CHAR (8)]