

SAP ABAP table CMS_STR_VEH_DATA_GET {Vehicles GET data - API Layer}

CMS_STR_VEH_DATA_GET-BANK_CNTRY_LIQ = T005-LAND1

CMS_STR_VEH_DATA_GET-MOV_MANU_CNTRY = T005-LAND1

CMS_STR_VEH_DATA_GET-PERM_WGHT_UNT = T006-MSEHI

CMS_STR_VEH_DATA_GET-UNIT_OF_MEASURE = T006-MSEHI

CMS_STR_VEH_DATA_GET

MOV_CATEGORY [CHAR (6)]

MOV_TYP [CHAR (6)]

MOV_LOC_DESC [CHAR (6)]

MOV_IDEN_TYP [CHAR (6)]

MOV_UOB [CHAR (6)]

MOV_MANU_CNTRY [CHAR (3)]

MOV_TYPE_FEAT [CHAR (6)]

PERM_WGHT_UNT [UNIT (3)]

SFTY_AMT_CURR [CUKY (5)]

LIQD_REASON [CHAR (6)]

LIQD_CURR [CUKY (5)]

EXP_PRCD_CURR [CUKY (5)]

BANK_CNTRY_LIQ [CHAR (3)]

NOM_VALUE_CURR [CUKY (5)]

AST_VALUE_CURR [CUKY (5)]

UNIT_OF_MEASURE [UNIT (3)]

PUR_PRICE_CURR [CUKY (5)]

0..N

1

1

0..N

1

0..N

1

1

1

1

1

0..N

1

0..N

10..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

T005
<u>MANDT</u> [CLNT (3)]
LAND1 [CHAR (3)]

T006
<u>MANDT</u> [CLNT (3)]
MSEHI [UNIT (3)]

TCMS_ATT_ID_TY
<u>MANDT</u> [CLNT (3)]
<u>INDICATOR_ID</u> [CHAR (6)]
INDICATOR_TYPE [CHAR (6)]

TCMS_MOV_TYP
<u>MANDT</u> [CLNT (3)]
<u>MOV_CATEGORY</u> [CHAR (6)]
MOV_TYP [CHAR (6)]

TCMS_OMS_FEAT
<u>MANDT</u> [CLNT (3)]
<u>CATEGORYID</u> [CHAR (6)]
TYPE_FEAT [CHAR (6)]

TCURC
<u>MANDT</u> [CLNT (3)]
<u>WAERS</u> [CUKY (5)]