

SAP ABAP table COCF_S_SN_LIST_FLAT {Shift Note}

COCF_S_SN_LIST_FLAT/SAPSMOSS/ADDID = /SAPSMOSS/ADDID-R3ADDID

SAPSMOSS_ADDID
MANDT [CLNT (3)]
R3ADDID [CHAR (10)]

COCF_S_SN_LIST_FLAT/SAPSMOSS/ADDREL = /SAPSMOSS/ADDRL-R3ADDREL

SAPSMOSS_ADDRL
MANDT [CLNT (3)]
R3ADDREL [CHAR (10)]

COCF_S_SN_LIST_FLAT/SAPSMOSS/DBSYS = /SAPSMOSS/DBSY-DBSYS

SAPSMOSS_DBSY
MANDT [CLNT (3)]
DBSYS [CHAR (10)]

COCF_S_SN_LIST_FLAT/SAPSMOSS/FRONT = /SAPSMOSS/FRNT-FRONTEND

SAPSMOSS_FRNT
MANDT [CLNT (3)]
FRONTEND [CHAR (10)]

COCF_S_SN_LIST_FLAT/SAPSMOSS/INSTN = /SAPSMOSS/INSTN-R3INSTN

SAPSMOSS_INSTN
MANDT [CLNT (3)]
R3INSTN [CHAR (10)]

COCF_S_SN_LIST_FLAT/SAPSMOSS/OSSYS = /SAPSMOSS/OSYS-OSSYS

SAPSMOSS_OSYS
MANDT [CLNT (3)]
OSSYS [CHAR (10)]

COCF_S_SN_LIST_FLAT/SAPSMOSS/REL = /SAPSMOSS/REL-R3REL

SAPSMOSS_REL
MANDT [CLNT (3)]
R3REL [CHAR (10)]

COCF_S_SN_LIST_FLAT/SAPSMOSS/STATUS = /SAPSMOSS/STAT-STATUS

SAPSMOSS_STAT
STATUS [CHAR (1)]

COCF_S_SN_LIST_FLAT/SAPSMOSS/SYSTYP = /SAPSMOSS/SYST-R3SYSTYPE

SAPSMOSS_SYST
MANDT [CLNT (3)]
R3SYSTYPE [CHAR (1)]

COCF_S_SN_LIST_FLAT-AUFNR = AUFK-AUFNR

AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

COCF_S_SN_LIST_FLAT-COAUFNR = AUFK-AUFNR

CRID
MANDT [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]

COCF_S_SN_LIST_FLAT-FERTAUFNR = AUFK-AUFNR

EKKO
MANDT [CLNT (3)]
EBELN [CHAR (10)]

COCF_S_SN_LIST_FLAT-EBELN = EKKO-EBELN

EKPO
MANDT [CLNT (3)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]

COCF_S_SN_LIST_FLAT-EBELP = EKPO-EBELP

COCF_S_SN_LIST_FLAT-KUNUM = KNA1-KUNNR

KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]

COCF_S_SN_LIST_FLAT-HERSTELLER = LFA1-LIFNR

LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]

COCF_S_SN_LIST_FLAT-LIFNUM = LFA1-LIFNR

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

COCF_S_SN_LIST_FLAT-EMATNR = MARA-MATNR

MCH1
MANDT [CLNT (3)]
MATNR [CHAR (18)]
CHARG [CHAR (10)]

COCF_S_SN_LIST_FLAT-MATNR = MARA-MATNR

MKAL
MANDT [CLNT (3)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
VERID [CHAR (4)]

COCF_S_SN_LIST_FLAT-CHARG = MCH1-CHARG

MKAL
MANDT [CLNT (3)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
VERID [CHAR (4)]

COCF_S_SN_LIST_FLAT-RM_MATNR = MKAL-MATNR

ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]

COCF_S_SN_LIST_FLAT-RM_WERKS = MKAL-WERKS

QALS
MANDANT [CLNT (3)]
PRUEFLOS [NUMC (12)]

COCF_S_SN_LIST_FLAT-VERID = MKAL-VERID

QMEL
MANDT [CLNT (3)]
QMNUM [CHAR (12)]

COCF_S_SN_LIST_FLAT-OBJNR = ONR00-OBJNR

QGR
MANDT [CLNT (3)]
KATALOGART [CHAR (2)]
CODEGRUPPE [CHAR (8)]

COCF_S_SN_LIST_FLAT-OBJNR_REAL = ONR00-OBJNR

SAFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

COCF_S_SN_LIST_FLAT-OBJNR_STAT = ONR00-OBJNR

T000
MANDT [CLNT (3)]

COCF_S_SN_LIST_FLAT-PRUEFLOS = QALS-PRUEFLOS

T001L
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LGORT [CHAR (4)]

COCF_S_SN_LIST_FLAT-QWRNUM = QMEL-QMNUM

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

COCF_S_SN_LIST_FLAT-QMGRP = QPGR-CODEGRUPPE

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

COCF_S_SN_LIST_FLAT-SA_AUFNR = SAFK-AUFNR

T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]

COCF_S_SN_LIST_FLAT-MANDT = T000-MANDT

T024
MANDT [CLNT (3)]
EKGRP [CHAR (3)]

COCF_S_SN_LIST_FLAT-LGORTCHARG = T001L-LGORT

T024E
MANDT [CLNT (3)]
EKORG [CHAR (4)]

COCF_S_SN_LIST_FLAT-LGORTVORG = T001L-LGORT

T179
MANDT [CLNT (3)]
PRODH [CHAR (18)]

COCF_S_SN_LIST_FLAT-ARBPLWERK = T001W-WERKS

T352B
MANDT [CLNT (3)]
RBNR [CHAR (9)]

COCF_S_SN_LIST_FLAT-MAWERK = T001W-WERKS

T356
MANDT [CLNT (3)]
ARTPR [CHAR (2)]
PRIOK [CHAR (1)]

COCF_S_SN_LIST_FLAT-MGEIN = T006-MSEHI

T356A
MANDT [CLNT (3)]
ARTPR [CHAR (2)]

COCF_S_SN_LIST_FLAT-PRDHA = T179-PROD

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

COCF_S_SN_LIST_FLAT-RBNR = T352B-RBNR

TQ15
MANDT [CLNT (3)]
KATALOGART [CHAR (2)]

COCF_S_SN_LIST_FLAT-PRIOK = T356-PRIOK

TQ80
MANDT [CLNT (3)]
QMART [CHAR (2)]

COCF_S_SN_LIST_FLAT-ARTPR = T356A-ARTPR

TQ81
MANDT [CLNT (3)]
AUSWIRK [CHAR (4)]

COCF_S_SN_LIST_FLAT-WAERS = TCURC-WAERS

TQ81V
MANDT [CLNT (3)]
TEILEV [CHAR (4)]

COCF_S_SN_LIST_FLAT-QMKAT = TQ15-KATALOGART

TQ86
MANDT [CLNT (3)]
FEART [CHAR (8)]

COCF_S_SN_LIST_FLAT-QMART = TQ80-QMART

TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]

COCF_S_SN_LIST_FLAT-AUSWIRK = TQ81-AUSWIRK

TTSEGTPLH
CLIENT [CLNT (3)]
TEPL [CHAR (10)]

COCF_S_SN_LIST_FLAT-TEILEV = TQ81V-TEILEV

TTZZ
CLIENT [CLNT (3)]
TZONE [CHAR (6)]

COCF_S_SN_LIST_FLAT-FEART = TQ86-FEART

TVBK
MANDT [CLNT (3)]
VKBUR [CHAR (4)]
VKGRP [CHAR (3)]

COCF_S_SN_LIST_FLAT-SPART = TSPA-SPART

TVBZ
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]
VKBUR [CHAR (4)]

COCF_S_SN_LIST_FLAT-TSEGTPLH = TTSEGTPLH-TEPL

TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]

COCF_S_SN_LIST_FLAT-TZONSO = TTZZ-TZONE

TVTW
MANDT [CLNT (3)]
VTWEG [CHAR (2)]

COCF_S_SN_LIST_FLAT-VKGRP = TVBK-VKGRP

VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]

COCF_S_SN_LIST_FLAT-VKBUR = TVBZ-VKBUR

VBUP
MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]

COCF_S_SN_LIST_FLAT-VKORG = TVKO-VKORG

COCF_S_SN_LIST_FLAT-VTWEG = TVTW-VTWEG

COCF_S_SN_LIST_FLAT-LS_KDAUF = VBUK-VBELN

COCF_S_SN_LIST_FLAT-LS_VBELN = VBUK-VBELN

COCF_S_SN_LIST_FLAT-VBELN = VBUK-VBELN

COCF_S_SN_LIST_FLAT-LS_KDPOS = VBUP-POSNR

COCF_S_SN_LIST_FLAT-LS_POSNR = VBUP-POSNR

COCF_S_SN_LIST_FLAT
MANDT [CLNT (3)]
QMART [CHAR (2)]
ARTPR [CHAR (2)]
PRIOK [CHAR (1)]
WAERS [CUKY (5)]
AUFNR [CHAR (12)]
VERID [CHAR (4)]
RM_MATNR [CHAR (18)]
RM_WERKS [CHAR (4)]
SA_AUFNR [CHAR (12)]
MATNR [CHAR (18)]
MATKL [CHAR (9)]
PRDHA [CHAR (18)]
KUNUM [CHAR (10)]
OBJNR [CHAR (22)]
RBNR [CHAR (9)]
LIFNUM [CHAR (10)]
VBELN [CHAR (10)]
SPART [CHAR (2)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
MAWERK [CHAR (4)]
QMKAT [CHAR (1)]
QMGRP [CHAR (8)]
AUSWIRK [CHAR (4)]
TEILEV [CHAR (4)]
PRUEFLOS [NUMC (12)]
CHARG [CHAR (10)]
LGORTCHARG [CHAR (4)]
HERSTELLER [CHAR (10)]
EMATNR [CHAR (18)]
EKORG [CHAR (4)]
BKGRP [CHAR (3)]
LGORTVORG [CHAR (4)]
FERTAUFNR [CHAR (12)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]
LS_KDAUF [CHAR (10)]
LS_KDPOS [NUMC (6)]
LS_VBELN [CHAR (10)]
LS_POSNR [NUMC (6)]
ARBPL [NUMC (8)]
ARBPLWERK [CHAR (4)]
FEART [CHAR (8)]
MGEIN [UNIT (3)]
COAUFNR [CHAR (12)]
QWRNUM [CHAR (12)]
VKBUR [CHAR (4)]
VKGRP [CHAR (3)]
TSEGTP [CHAR (10)]
TZONSO [CHAR (6)]
SAPSMOSS_INSTN [CHAR (10)]
SAPSMOSS_OSSYS [CHAR (10)]
SAPSMOSS_DBSYS [CHAR (10)]
SAPSMOSS_REL [CHAR (10)]
SAPSMOSS_FRONT [CHAR (10)]
SAPSMOSS_SYSTYP [CHAR (1)]
SAPSMOSS_ADDID [CHAR (10)]
SAPSMOSS_ADDREL [CHAR (10)]
SAPSMOSS_STATUS [CHAR (1)]
OBJNR_REAL [CHAR (22)]
OBJNR_STAT [CHAR (22)]