

SAP ABAP table COPABBSEG_GLX {FI-SL: Interface for CO-PA plan data}

COPABBSEG_GLX
RKE_ARTNR [CHAR (18)]
RKE_BONUS [CHAR (2)]
RKE_BRSCH [CHAR (4)]
RKE_BUKRS [CHAR (4)]
RKE_BZIRK [CHAR (6)]
RKE_EFORM [CHAR (5)]
RKE_FKART [CHAR (4)]
RKE_GEBIE [CHAR (4)]
RKE_GSBER [CHAR (4)]
RKE_KAUFN [CHAR (10)]
RKE_KDGRP [CHAR (2)]
RKE_KNDNR [CHAR (10)]
RKE_KOKRS [CHAR (4)]
RKE_LAND1 [CHAR (3)]
RKE_MAABC [CHAR (1)]
RKE_MATKL [CHAR (9)]
RKE_SPART [CHAR (2)]
RKE_VKBUR [CHAR (4)]
RKE_VKGRP [CHAR (3)]
RKE_VKORG [CHAR (4)]
RKE_VTWEG [CHAR (2)]
RKE_WERKS [CHAR (4)]

COPABBSEG_GLX-RKE_KNDNR = KNA1-KUNNR

0..N

KNA1
<u>MANDT</u> [CLNT (3)]
<u>KUNNR</u> [CHAR (10)]

COPABBSEG_GLX-RKE_ARTNR = MARA-MATNR

0..N

MARA
<u>MANDT</u> [CLNT (3)]
<u>MATNR</u> [CHAR (18)]

COPABBSEG_GLX-RKE_BUKRS = T001-BUKRS

0..N

T001
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]

COPABBSEG_GLX-RKE_WERKS = T001W-WERKS

0..N

T001W
<u>MANDT</u> [CLNT (3)]
<u>WERKS</u> [CHAR (4)]

COPABBSEG_GLX-RKE_LAND1 = T005-LAND1

0..N

T005
<u>MANDT</u> [CLNT (3)]
<u>LAND1</u> [CHAR (3)]

COPABBSEG_GLX-RKE_BRSCH = T016-BRSCH

0..N

T016
<u>MANDT</u> [CLNT (3)]
<u>BRSCH</u> [CHAR (4)]

COPABBSEG_GLX-RKE_MATKL = T023-MATKL

0..N

T023
<u>MANDT</u> [CLNT (3)]
<u>MATKL</u> [CHAR (9)]

COPABBSEG_GLX-RKE_KDGRP = T151-KDGRP

0..N

T151
<u>MANDT</u> [CLNT (3)]
<u>KDGRP</u> [CHAR (2)]

COPABBSEG_GLX-RKE_BZIRK = T171-BZIRK

0..N

T171
<u>MANDT</u> [CLNT (3)]
<u>BZIRK</u> [CHAR (6)]

COPABBSEG_GLX-RKE_EFORM = T2513-EFORM

0..N

T2513
<u>MANDT</u> [CLNT (3)]
<u>EFORM</u> [CHAR (5)]

COPABBSEG_GLX-RKE_GEBIE = T2538-GEBIE

0..N

T2538
<u>MANDT</u> [CLNT (3)]
<u>GEBIE</u> [CHAR (4)]

COPABBSEG_GLX-RKE_GSBER = TGSB-GSBER

0..N

TGSB
<u>MANDT</u> [CLNT (3)]
<u>GSBER</u> [CHAR (4)]

COPABBSEG_GLX-RKE_KOKRS = TKA01-KOKRS

0..N

TKA01
<u>MANDT</u> [CLNT (3)]
<u>KOKRS</u> [CHAR (4)]

COPABBSEG_GLX-RKE_MAABC = TMABC-MAABC

0..N

TMABC
<u>MANDT</u> [CLNT (3)]
<u>MAABC</u> [CHAR (1)]

COPABBSEG_GLX-RKE_SPART = TSPA-SPART

0..N

TSPA
<u>MANDT</u> [CLNT (3)]
<u>SPART</u> [CHAR (2)]

COPABBSEG_GLX-RKE_BONUS = TVBO-BONUS

0..N

TVBO
<u>MANDT</u> [CLNT (3)]
<u>BONUS</u> [CHAR (2)]

COPABBSEG_GLX-RKE_VKBUR = TVBUR-VKBUR

0..N

TVBUR
<u>MANDT</u> [CLNT (3)]
<u>VKBUR</u> [CHAR (4)]

COPABBSEG_GLX-RKE_FKART = TVFK-FKART

0..N

TVFK
<u>MANDT</u> [CLNT (3)]
<u>FKART</u> [CHAR (4)]

COPABBSEG_GLX-RKE_VKGRP = TVKGR-VKGRP

0..N

TVKGR
<u>MANDT</u> [CLNT (3)]
<u>VKGRP</u> [CHAR (3)]

COPABBSEG_GLX-RKE_VKORG = TVKO-VKORG

0..N

TVKO
<u>MANDT</u> [CLNT (3)]
<u>VKORG</u> [CHAR (4)]

COPABBSEG_GLX-RKE_VTWEG = TVTW-VTWEG

0..N

TVTW
<u>MANDT</u> [CLNT (3)]
<u>VTWEG</u> [CHAR (2)]

COPABBSEG_GLX-RKE_KAUFN = VBUK-VBELN

0..N

VBUK
<u>MANDT</u> [CLNT (3)]
<u>VBELN</u> [CHAR (10)]

11111111

11111111

11111111

11111111

11111111

11111111

11111111

11111111

11111111

11111111

11111111

11111111

11111111

11111111

11111111

11111111

11111111

11111111

11111111

11111111