

SAP ABAP table COWB_S_HEADER {Display Structure for Order Headers}

COWB_S_HEADER-AENNR = AENR-AENNR

COWB_S_HEADER-PAENR = AENR-AENNR

COWB_S_HEADER-SAENR = AENR-AENNR

COWB_S_HEADER-AUFNR = AUFK-AUFNR

COWB_S_HEADER-LKNOT = AUFK-AUFNR

COWB_S_HEADER-MAUFNR = AUFK-AUFNR

COWB_S_HEADER-REFNR = AUFK-AUFNR

COWB_S_HEADER-RKNOT = AUFK-AUFNR

COWB_S_HEADER-PRCTR = CEPC-PRCTR

COWB_S_HEADER-RSHID = CRID-OBJID

COWB_S_HEADER-RSNID = CRID-OBJID

COWB_S_HEADER-AKSTL = CSKS-KOSTL

COWB_S_HEADER-BEDID = KBKO-BEDID

COWB_S_HEADER-GROID = KBKO-BEDID

COWB_S_HEADER-RATID = KBKO-BEDID

COWB_S_HEADER-CSPLIT = MAKV-CSPLIT

COWB_S_HEADER-M_BAUGR = MARA-MATNR

COWB_S_HEADER-PLNBEZ = MARA-MATNR

COWB_S_HEADER-STLBEZ = MARA-MATNR

COWB_S_HEADER-OBJNR = ONR00-OBJNR

COWB_S_HEADER-PROJN = PRPS-PSPNR

COWB_S_HEADER-PSPEL = PRPS-PSPNR

COWB_S_HEADER-PRUEFLOS = QALS-PRUEFLOS

COWB_S_HEADER-ARSNR = RESB-RSNUM

COWB_S_HEADER-RSNUM = RESB-RSNUM

COWB_S_HEADER-MANDT = T000-MANDT

COWB_S_HEADER-ABUKR = T001-BUKRS

COWB_S_HEADER-BUKRS = T001-BUKRS

COWB_S_HEADER-SOWRK = T001W-WERKS

COWB_S_HEADER-WERKS = T001W-WERKS

COWB_S_HEADER-AUART = T003O-AUART

COWB_S_HEADER-BMEINS = T006-MSEHI

COWB_S_HEADER-CFB_LZEIH = T006-MSEHI

COWB_S_HEADER-CONF_REM_UNIT = T006-MSEHI

COWB_S_HEADER-CONF_UNIT = T006-MSEHI

COWB_S_HEADER-GMEIN = T006-MSEHI

COWB_S_HEADER-PLNME = T006-MSEHI

COWB_S_HEADER-SBMEH = T006-MSEHI

COWB_S_HEADER-PLGRP = T024A-FEVR

COWB_S_HEADER-DISPO = T024D-DISPO

COWB_S_HEADER-FEVR = T024F-FEVR

COWB_S_HEADER-IZWEK = T087I-IZWEK

COWB_S_HEADER-UMWKZ = T087K-UMWKZ

COWB_S_HEADER-PVERW = T411-VERWE

COWB_S_HEADER-STLST = T415S-STLST

COWB_S_HEADER-STLAN = T416-STLAN

COWB_S_HEADER-FHORI = T436A-FHORI

COWB_S_HEADER-TERKZ = T482-TERMKZ

COWB_S_HEADER-TRKZP = T482-TERMKZ

COWB_S_HEADER-KAPPL = T681A-KAPPL

COWB_S_HEADER-KVEWE = T681V-KVEWE

COWB_S_HEADER-CHSCH = T683-KALSM

COWB_S_HEADER-KALSM = T683-KALSM

COWB_S_HEADER-JV_JIBCL = T8J6A-CLASS

COWB_S_HEADER-JV_JBSA = T8J6C-SUBCLASS

COWB_S_HEADER-ETYPE = T8JG-ETYPE

COWB_S_HEADER-RECID = T8JJ-RECID

COWB_S_HEADER-VNAME = T8JV-VNAME

COWB_S_HEADER-SIZECL = TAIF5-SIZECL

COWB_S_HEADER-IVPRO = TAPRF-IVPRO

COWB_S_HEADER-BEMOT = TBMOT-BEMOT

COWB_S_HEADER-KAPVERSA = TC36-VERSN

COWB_S_HEADER-PLNTY = TCA01-PLNTY

COWB_S_HEADER-PLNAW = TCA09-PLNAW

COWB_S_HEADER-KLVARI = TCK03-KLVAR

COWB_S_HEADER-KLVARP = TCK03-KLVAR

COWB_S_HEADER-PROFID = TCN41-PROFIDNETZ

COWB_S_HEADER-SFCPF = TCO43-CO_PRODPRF

COWB_S_HEADER-WAERS = TCURC-WAERS

COWB_S_HEADER-CALID = TFACD-IDENT

COWB_S_HEADER-FUNC_AREA = TFKB-FKBER

COWB_S_HEADER-GSBER = TGSB-GSBER

COWB_S_HEADER-STATS = TJ20-STSMA

COWB_S_HEADER-KOKRS = TKA01-KOKRS

COWB_S_HEADER-ABGSL = TKKAA-ABGSL

COWB_S_HEADER-ABKRS = TKO08-ABKRS

COWB_S_HEADER-AWSLS = TKV01-AWSLS

COWB_S_HEADER-TXJCD = TTXX-TXJCD

COWB_S_HEADER-KDAUF_AUFK = VBUK-VBELN

AENR

MANDT [CLNT (3)]

AENNR [CHAR (12)]

AUFK

MANDT [CLNT (3)]

AUFNR [CHAR (12)]

CEPC

MANDT [CLNT (3)]

PRCTR [CHAR (10)]

DATBI [DATS (8)]

KOKRS [CHAR (4)]

CRID

MANDT [CLNT (3)]

OBJTY [CHAR (2)]

OBJID [NUMC (8)]

CSKS

MANDT [CLNT (3)]

KOKRS [CHAR (4)]

KOSTL [CHAR (10)]

DATBI [DATS (8)]

KBKO

MANDT [CLNT (3)]

BEDID [NUMC (12)]

MAKV

MANDT [CLNT (3)]

MATNR [CHAR (18)]

WERKS [CHAR (4)]

CSPLIT [CHAR (4)]

MARA

MANDT [CLNT (3)]

MATNR [CHAR (18)]

ONR00

MANDT [CLNT (3)]

OBJNR [CHAR (22)]

PRPS

MANDT [CLNT (3)]

PSPNR [NUMC (8)]

QALS

MANDANT [CLNT (3)]

PRUEFLOS [NUMC (12)]

RESB

MANDT [CLNT (3)]

RSNUM [NUMC (10)]

RSPOS [NUMC (4)]

RSART [CHAR (1)]

T000

MANDT [CLNT (3)]

T001

MANDT [CLNT (3)]

BUKRS [CHAR (4)]

T001W

MANDT [CLNT (3)]

WERKS [CHAR (4)]

T003O

CLIENT [CLNT (3)]

AUART [CHAR (4)]

T006

MANDT [CLNT (3)]

MSEHI [UNIT (3)]

T024A

MANDT [CLNT (3)]

WERKS [CHAR (4)]

FEVR [CHAR (3)]

T024D

MANDT [CLNT (3)]

WERKS [CHAR (4)]

DISPO [CHAR (3)]

T024F

MANDT [CLNT (3)]

WERKS [CHAR (4)]

FEVR [CHAR (3)]

T087I

MANDT [CLNT (3)]

IZWEK [CHAR (2)]

T087K

MANDT [CLNT (3)]

UMWKZ [CHAR (5)]

T411

MANDT [CLNT (3)]

VERWE [CHAR (3)]

T415S

MANDT [CLNT (3)]

STLST [NUMC (2)]

T416

MANDT [CLNT (3)]

STLAN [CHAR (1)]

T436A

MANDT [CLNT (3)]

WERKS [CHAR (4)]

FHORI [CHAR (3)]

T482

MANDT [CLNT (3)]

TERMKZ [CHAR (1)]

T681A

KAPPL [CHAR (2)]

T681V

KVEWE [CHAR (1)]

T683

MANDT [CLNT (3)]

KVEWE [CHAR (1)]

KAPPL [CHAR (2)]

KALSM [CHAR (6)]

T8J6A

MANDT [CLNT (3)]

BUKRS [CHAR (4)]

CLASS [CHAR (3)]

T8J6C

MANDT [CLNT (3)]

BUKRS [CHAR (4)]

CLASS [CHAR (3)]

SUBCLASS [CHAR (5)]

T8JG

MANDT [CLNT (3)]

BUKRS [CHAR (4)]

VNAME [CHAR (6)]

ETYPE [CHAR (3)]

EDATE [NUMC (8)]

T8JJ

MANDT [CLNT (3)]

BUKRS [CHAR (4)]

RECID [CHAR (2)]

T8JV

MANDT [CLNT (3)]

BUKRS [CHAR (4)]

VNAME [CHAR (6)]

TAIF5

MANDT [CLNT (3)]

SIZECL [CHAR (2)]

TAPRF

MANDT [CLNT (3)]

IVPRO [CHAR (6)]

TBMOT

MANDT [CLNT (3)]

BEMOT [CHAR (2)]

TC36

MANDT [CLNT (3)]

VERSN [NUMC (2)]

TCA01

MANDT [CLNT (3)]

PLNTY [CHAR (1)]

TCA09

MANDT [CLNT (3)]

PLNAW [CHAR (1)]

TCK03

MANDT [CLNT (3)]

KLVAR [CHAR (4)]

TCN41

MANDT [CLNT (3)]

PLNAW [CHAR (1)]

PROFIDNETZ [CHAR (7)]

TCO43

MANDT [CLNT (3)]

WERKS [CHAR (4)]

CO_PRODPRF [CHAR (6)]

TCURC

MANDT [CLNT (3)]

WAERS [CUKY (5)]

TFACD

IDENT [CHAR (2)]

TFKB

MANDT [CLNT (3)]

EKBER [CHAR (16)]

TGSB

MANDT [CLNT (3)]

GSBER [CHAR (4)]

TJ20

MANDT [CLNT (3)]

STSMA [CHAR (8)]

TKA01

MANDT [CLNT (3)]

KOKRS [CHAR (4)]

TKKAA

MANDT [CLNT (3)]

ABGSL [CHAR (6)]

TKO08

CLIENT [CLNT (3)]

KOKRS [CHAR (4)]

ABKRS [NUMC (2)]

TKV01

MANDT [CLNT (3)]

AWOBA [CHAR (2)]

AWSLS [CHAR (6)]

TTXJ

MANDT [CLNT (3)]

KALSM [CHAR (6)]

TXJCD [CHAR (15)]

VBUK

MANDT [CLNT (3)]

VBELN [CHAR (10)]

COWB_S_HEADER

MANDT [CLNT (3)]

AUFNR [CHAR (12)]

WERKS [CHAR (4)]

DISPO [CHAR (3)]

FEVR [CHAR (3)]

PVERW [CHAR (3)]

PLNBEZ [CHAR (18)]

PLNAW [CHAR (1)]

PLNTY [CHAR (1)]

PLGRP [CHAR (3)]

PLNME [UNIT (3)]

PAENR [CHAR (12)]

STLST [NUMC (2)]

STLAN [CHAR (1)]

SBMEH [UNIT (3)]

SAENR [CHAR (12)]

STLBEZ [CHAR (18)]

RSNUM [NUMC (10)]

GMEIN [UNIT (3)]

TERKZ [CHAR (1)]

FHORI [CHAR (3)]

AUART [CHAR (4)]

REFNR [CHAR (12)]

BUKRS [CHAR (4)]