

SAP ABAP table CRMC_LEASING_FC {CRM Leasing: Control of Whether Field Is Ready for Input}

CRMC_LEASING_FC-PRIORITY = CRMC_CHGLEVEL-CHANGELEVEL

CRMC_CHGLEVEL
<u>MANDT</u> [CLNT (3)]
<u>CHANGELEVEL</u> [NUMC (3)]

CRMC_LEASING_FC-ITM_TYPE = CRMC_ITEM_TYPE-ITM_TYPE

CRMC_ITEM_TYPE
<u>CLIENT</u> [CLNT (3)]
<u>ITM_TYPE</u> [CHAR (4)]

CRMC_LEASING_FC-OBJECTNAME = CRMC_OBJECTS-NAME

CRMC_OBJECTS
<u>NAME</u> [CHAR (30)]

CRMC_LEASING_FC-PROCESS_TYP = CRMC_PROC_TYPE-PROCESS_TYPE

CRMC_PROC_TYPE
<u>CLIENT</u> [CLNT (3)]
<u>PROCESS_TYPE</u> [CHAR (4)]

CRMC_LEASING_FC-FIELDNAME = DD03L-FIELDNAME

DD03L
<u>TABNAME</u> [CHAR (30)]
<u>FIELDNAME</u> [CHAR (30)]
<u>AS4LOCAL</u> [CHAR (1)]
<u>AS4VERS</u> [NUMC (4)]
<u>POSITION</u> [NUMC (4)]

CRMC_LEASING_FC-ISTAT1 = TJ02-ISTAT

CRMC_LEASING_FC-ISTAT2 = TJ02-ISTAT

CRMC_LEASING_FC-ISTAT3 = TJ02-ISTAT

CRMC_LEASING_FC-ISTAT4 = TJ02-ISTAT

CRMC_LEASING_FC-ISTAT5 = TJ02-ISTAT

TJ02
<u>ISTAT</u> [CHAR (5)]

CRMC_LEASING_FC
<u>MANDT</u> [CLNT (3)]
<u>PROCESS_TYP</u> [CHAR (4)]
<u>ITM_TYPE</u> [CHAR (4)]
<u>OBJECTNAME</u> [CHAR (30)]
<u>FIELDNAME</u> [CHAR (30)]
<u>ISTAT1</u> [CHAR (5)]
<u>ISTAT2</u> [CHAR (5)]
<u>ISTAT3</u> [CHAR (5)]
<u>ISTAT4</u> [CHAR (5)]
<u>ISTAT5</u> [CHAR (5)]
<u>PRIORITY</u> [NUMC (3)]