SAP ABAP table CRMS_MKTPL_EAI_TS {Trade Spends data holder for EAI}

CRMS_MKTPL_EAI_TS-PROJECT_GUID = CGPL_PROJECT-GUID

CGPL_PROJECT

CLIENT [CLNT (3)]
GUID [RAW (16)]

0..N

CRMS_MKTPL_EAI_TS-TASK_GUID = CGPL_TASK-GUID

CGPL_TASK

CLIENT [CLNT (3)]
GUID [RAW (16)]

0..N

CRMS_MKTPL_EAI_TS-COST_CATEGORY = CRMC_MKTPL_COS0-COST_CATEGORY

CRMC_MKTPL_COS0

CLIENT [CLNT (3)]
APPLICATION [CHAR (3)]
COST_CATEGORY [CHAR (30)]

0..N

CRMS_MKTPL_EAI_TS

CLIENT [CLNT (3)]
PROJECT_GUID [RAW (16)]
TASK_GUID [RAW (16)]
COST_TYPE [CHAR (4)]
COST_CATEGORY [CHAR (30)]
SPEND_METHOD [CHAR (10)]
DISC_METHOD [CHAR (4)]
VOLUME [CHAR (4)]

0..N   0..N

CRMS_MKTPL_EAI_TS-SPEND_METHOD = CRMC_MKTPL_COS1-SPEND_METHOD

CRMC_MKTPL_COS1

CLIENT [CLNT (3)]
APPLICATION [CHAR (3)]
SPEND_METHOD [CHAR (10)]

0..N

0..N

CRMS_MKTPL_EAI_TS-VOLUME = CRMC_MKTPL_COS5-VOLUME

0..N

CRMC_MKTPL_COS5

CLIENT [CLNT (3)]
APPLICATION [CHAR (3)]
VOLUME [CHAR (4)]

0..N

CRMS_MKTPL_EAI_TS-COST_TYPE = CRMC_MKTPL_COST-COST_TYPE

0..N

CRMC_MKTPL_COST

CLIENT [CLNT (3)]
APPLICATION [CHAR (3)]
COST_TYPE [CHAR (4)]

0..N   0..N

CRMS_MKTPL_EAI_TS-DISC_METHOD = CRMC_MKTPL_DISC-DISC_METHOD

0..N

CRMC_MKTPL_DISC

CLIENT [CLNT (3)]
APPLICATION [CHAR (3)]
DISC_METHOD [CHAR (4)]

0..N

CRMS_MKTPL_EAI_TS-CLIENT = T000-MANDT

T000

MANDT [CLNT (3)]

0..N