

SAP ABAP table CRMV\_PROD\_FIN02H {Generated Table for View}

| CRMV_PROD_FIN02H                    |
|-------------------------------------|
| <u>CLIENT</u> [CLNT (3)]            |
| <u>FRG_GUID</u> [RAW (16)]          |
| <u>VALID_TO</u> [DEC (15)]          |
| <u>VALID_FROM</u> [DEC (15)]        |
| <u>UPNAME</u> [CHAR (12)]           |
| <u>PAYMENT_FREQUEN</u> [NUMC (2)]   |
| <u>PAYMENT_FORM</u> [NUMC (1)]      |
| <u>DOWN_PAYMENT_F</u> [CHAR (1)]    |
| <u>STEP_PAYMENT_F</u> [CHAR (1)]    |
| <u>INTERIM_PERIOD</u> [NUMC (2)]    |
| <u>REFERENCE_INTER</u> [NUMC (2)]   |
| <u>REFERENCE_INTE_D</u> [CHAR (10)] |
| <u>LOOKUP_FOR_INTER</u> [NUMC (2)]  |
| <u>TIMEUNIT</u> [CHAR (12)]         |
| <u>TERM</u> [NUMC (3)]              |
| <u>RATE_PER_K_USE</u> [CHAR (1)]    |
| <u>ROUND_PROFILE</u> [CHAR (12)]    |
| <u>CFTYPE_PROFILE</u> [CHAR (12)]   |
| <u>PRODUCT_GUID</u> [RAW (16)]      |
| <u>FRAGMENT_TYPE</u> [RAW (16)]     |
| <u>SALES_ORG</u> [CHAR (14)]        |
| <u>DISTR_CHAN</u> [CHAR (2)]        |

| CRMV_PROD_FIN02H-CFTYPE_PROFILE = CRMC_CFTYPE_PR_R-CFTYPE_PROFIL |
|------------------------------------------------------------------|
| <u>CLIENT</u> [CLNT (3)]                                         |
| <u>SALES_ORG</u> [CHAR (14)]                                     |
| <u>DISTR_CHAN</u> [CHAR (2)]                                     |
| <u>CFTYPE_PROFIL</u> [CHAR (12)]                                 |

| CRMV_PROD_FIN02H-PAYMENT_FORM = CRMC_PAYMFORM-PAYMFORM |
|--------------------------------------------------------|
| <u>PAYMFORM</u> [NUMC (1)]                             |

| CRMV_PROD_FIN02H-ROUND_PROFILE = CRMC_ROUND_PROFR-ROUND_PROFILE |
|-----------------------------------------------------------------|
| <u>CLIENT</u> [CLNT (3)]                                        |
| <u>SALES_ORG</u> [CHAR (14)]                                    |
| <u>DISTR_CHAN</u> [CHAR (2)]                                    |
| <u>ROUND_PROFILE</u> [CHAR (12)]                                |

| CRMV_PROD_FIN02H-REFERENCE_INTE_D = T056R-REFERENZ |
|----------------------------------------------------|
| <u>MANDT</u> [CLNT (3)]                            |
| <u>REFERENZ</u> [CHAR (10)]                        |

| CRMV_PROD_FIN02H-TIMEUNIT = TIMECUUT-NAME_UNIT |
|------------------------------------------------|
| <u>CLIENT</u> [CLNT (3)]                       |
| <u>NAME_UNIT</u> [CHAR (12)]                   |

