

SAP ABAP table CXMO_CAUFVD_O {Structure for Scheduling Monitor (Subnetworks): Issue}

CXMO_CAUFVD_O-AENNR = AENR-AENNR

CXMO_CAUFVD_O-PAENR = AENR-AENNR

CXMO_CAUFVD_O-SAENR = AENR-AENNR

CXMO_CAUFVD_O-ANLUN = ANLA-ANLN2

CXMO_CAUFVD_O-ANLNR = ANLH-ANLN1

CXMO_CAUFVD_O-AUFNR = AUFK-AUFNR

CXMO_CAUFVD_O-DAUFN = AUFK-AUFNR

CXMO_CAUFVD_O-IAUFNR = AUFK-AUFNR

CXMO_CAUFVD_O-LAUFN = AUFK-AUFNR

CXMO_CAUFVD_O-LKNOT = AUFK-AUFNR

CXMO_CAUFVD_O-MAUFNR = AUFK-AUFNR

CXMO_CAUFVD_O-REFNR = AUFK-AUFNR

CXMO_CAUFVD_O-RKNOT = AUFK-AUFNR

CXMO_CAUFVD_O-PRCTR = CEPK-PRCTR

CXMO_CAUFVD_O-GEWRK = CRID-OBJID

CXMO_CAUFVD_O-PPSID = CRID-OBJID

CXMO_CAUFVD_O-RSHID = CRID-OBJID

CXMO_CAUFVD_O-RSNID = CRID-OBJID

CXMO_CAUFVD_O-AKSTL = CSKS-KOSTL

CXMO_CAUFVD_O-KOSTL = CSKS-KOSTL

CXMO_CAUFVD_O-EQUNR = EQUI-EQUNR

CXMO_CAUFVD_O-TPLNR = IFLOT-TPLNR

CXMO_CAUFVD_O-ILOAN = ILOA-ILOAN

CXMO_CAUFVD_O-BEDID = KBKO-BEDID

CXMO_CAUFVD_O-GROID = KBKO-BEDID

CXMO_CAUFVD_O-RATID = KBKO-BEDID

CXMO_CAUFVD_O-KUNUM = KNA1-KUNNR

CXMO_CAUFVD_O-CSPLIT = MAKV-CSPLIT

CXMO_CAUFVD_O-BAUTL = MARA-MATNR

CXMO_CAUFVD_O-MATNR = MARA-MATNR

CXMO_CAUFVD_O-M_BAUGR = MARA-MATNR

CXMO_CAUFVD_O-PLNBEZ = MARA-MATNR

CXMO_CAUFVD_O-STLBEZ = MARA-MATNR

CXMO_CAUFVD_O-WARPL = MPLA-WARPL

CXMO_CAUFVD_O-OBJNR = ONR00-OBJNR

CXMO_CAUFVD_O-PKNUM = PKHD-PKNUM

CXMO_CAUFVD_O-PROID = PRPS-PSPNR

CXMO_CAUFVD_O-PROJN = PRPS-PSPNR

CXMO_CAUFVD_O-PSPEL = PRPS-PSPNR

CXMO_CAUFVD_O-PRUEFLOS = QALS-PRUEFLOS

CXMO_CAUFVD_O-QMNUM = QMEL-QMNUM

CXMO_CAUFVD_O-ARSNR = RESB-RSNUM

CXMO_CAUFVD_O-RSNUM = RESB-RSNUM

CXMO_CAUFVD_O-MANDT = T000-MANDT

CXMO_CAUFVD_O-ABUKR = T001-BUKRS

CXMO_CAUFVD_O-BUKRS = T001-BUKRS

CXMO_CAUFVD_O-IBUKRS = T001-BUKRS

CXMO_CAUFVD_O-SOWRK = T001W-WERKS

CXMO_CAUFVD_O-SWERK = T001W-WERKS

CXMO_CAUFVD_O-VAWRK = T001W-WERKS

CXMO_CAUFVD_O-WERKS = T001W-WERKS

CXMO_CAUFVD_O-AUART = T0030-AUART

CXMO_CAUFVD_O-NUART = T0030-AUART

CXMO_CAUFVD_O-BMEINS = T006-MSEHI

CXMO_CAUFVD_O-CFB_LZEIH = T006-MSEHI

CXMO_CAUFVD_O-GAUHE = T006-MSEHI

CXMO_CAUFVD_O-GMEIN = T006-MSEHI

CXMO_CAUFVD_O-PLNME = T006-MSEHI

CXMO_CAUFVD_O-SBMEH = T006-MSEHI

CXMO_CAUFVD_O-APGRP = T024A-FEVR

CXMO_CAUFVD_O-PLGRP = T024A-FEVR

CXMO_CAUFVD_O-DISPO = T024D-DISPO

CXMO_CAUFVD_O-VERAN = T024D-DISPO

CXMO_CAUFVD_O-FEVR = T024F-FEVR

CXMO_CAUFVD_O-INGRP = T024I-INGRP

CXMO_CAUFVD_O-IZWEK = T087I-IZWEK

CXMO_CAUFVD_O-UMWKZ = T087K-UMWKZ

CXMO_CAUFVD_O-REVRN = T352R-REVRN

CXMO_CAUFVD_O-ILART = T353I-ILART

CXMO_CAUFVD_O-PRIOK = T356-PRIOK

CXMO_CAUFVD_O-ARTPR = T356A-ARTPR

CXMO_CAUFVD_O-BEBER = T357-BEBER

CXMO_CAUFVD_O-ANLZU = T357M-ANLZU

CXMO_CAUFVD_O-ABCKZ = T370C-ABCKZ

CXMO_CAUFVD_O-IWERK = T399I-IWERK

CXMO_CAUFVD_O-PVERW = T411-VERWE

CXMO_CAUFVD_O-STLST = T415S-STLST

CXMO_CAUFVD_O-STLAN = T416-STLAN

CXMO_CAUFVD_O-FHORI = T436A-FHORI

CXMO_CAUFVD_O-PRREG = T441R-PRREG

CXMO_CAUFVD_O-TERKZ = T482-TERMKZ

CXMO_CAUFVD_O-TRKZP = T482-TERMKZ

CXMO_CAUFVD_O-STORT = T499S-STAND

CXMO_CAUFVD_O-KAPPL = T681A-KAPPL

CXMO_CAUFVD_O-KVEWE = T681V-KVEWE

CXMO_CAUFVD_O-CHSCH = T683-KALSM

CXMO_CAUFVD_O-KALSM = T683-KALSM

CXMO_CAUFVD_O-PLVAR = T778P-PLVAR

CXMO_CAUFVD_O-JV_JIBCL = T8J6A-CLASS

CXMO_CAUFVD_O-JV_JIBSA = T8J6C-SUBCLASS

CXMO_CAUFVD_O-ETYPE = T8JG-ETYPE

CXMO_CAUFVD_O-RECID = T8JJ-RECID

CXMO_CAUFVD_O-VNAME = T8JV-VNAME

CXMO_CAUFVD_O-SIZECL = TAI5-SIZECL

CXMO_CAUFVD_O-IVPRO = TAPRF-IVPRO

CXMO_CAUFVD_O-BEMOT = TBMOT-BEMOT

CXMO_CAUFVD_O-KAPVERSA = TC36-VERSN

CXMO_CAUFVD_O-PLNTY = TCA01-PLNTY

CXMO_CAUFVD_O-PLNAW = TCA09-PLNAW

CXMO_CAUFVD_O-KIVAR = TCK03-KIVAR

CXMO_CAUFVD_O-KIVARP = TCK03-KIVAR

CXMO_CAUFVD_O-PROFID = TCN41-PROFIDNETZ

CXMO_CAUFVD_O-SFCPF = TCO43-CO_PRODPRF

CXMO_CAUFVD_O-WAERS = TCURC-WAERS

CXMO_CAUFVD_O-CALID = TFACD-IDENT

CXMO_CAUFVD_O-FUNC_AREA = TFKB-FKBER

CXMO_CAUFVD_O-GSBER = TGSB-GSBER

CXMO_CAUFVD_O-IGSBER = TGSB-GSBER

CXMO_CAUFVD_O-STATS = TJ20-STMSA

CXMO_CAUFVD_O-IKOKRS = TKA01-KOKRS

CXMO_CAUFVD_O-KOKRS = TKA01-KOKRS

CXMO_CAUFVD_O-ABGSL = TKKAA-ABGSL

CXMO_CAUFVD_O-ABKRS = TKO08-ABKRS

CXMO_CAUFVD_O-AWSLS = TKV01-AWSLS

CXMO_CAUFVD_O-TSPART = TSPA-SPART

CXMO_CAUFVD_O-TXJCD = TTXJ-TXJCD

CXMO_CAUFVD_O-VKORG = TVKO-VKORG

CXMO_CAUFVD_O-VTWEG = TVTW-VTWEG

CXMO_CAUFVD_O-KDAUF_AUFK = VBUS-VBELN

AENR
MANDT [CLNT (3)]
AENNR [CHAR (12)]

ANLA
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
ANLN1 [CHAR (12)]
ANLN2 [CHAR (4)]

ANLH
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
ANLN1 [CHAR (12)]

AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

CEPK
MANDT [CLNT (3)]
PRCTR [CHAR (10)]
DATBI [DATS (8)]
KOKRS [CHAR (4)]

CRID
MANDT [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]

CSKS
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]

EQUI
MANDT [CLNT (3)]
EQUNR [CHAR (18)]

IFLOT
MANDT [CLNT (3)]
TPLNR [CHAR (30)]

ILOA
MANDT [CLNT (3)]
ILOAN [CHAR (12)]

KBKO
MANDT [CLNT (3)]
BEDID [NUMC (12)]

KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]

MAKV
MANDT [CLNT (3)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
CSPLIT [CHAR (4)]

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

MPLA
MANDT [CLNT (3)]
WARPL [CHAR (12)]

ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]

PKHD
MANDT [CLNT (3)]
PKNUM [CHAR (7)]

PRPS
MANDT [CLNT (3)]
PSPNR [NUMC (8)]

QALS
MANDT [CLNT (3)]
PRUEFLOS [NUMC (12)]

QMEL
MANDT [CLNT (3)]
QMNUM [CHAR (12)]

RESB
MANDT [CLNT (3)]
RSNUM [NUMC (10)]
RSPOS [NUMC (4)]
RSART [CHAR (1)]

T000
MANDT [CLNT (3)]

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

T0030
CLIENT [CLNT (3)]
AUART [CHAR (4)]

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

T024A
MANDT [CLNT (3)]
WERKS [CHAR (4)]
FEVR [CHAR (3)]

T024D
MANDT [CLNT (3)]
WERKS [CHAR (4)]
DISPO [CHAR (3)]

T024F
MANDT [CLNT (3)]
WERKS [CHAR (4)]
FEVR [CHAR (3)]

T024I
MANDT [CLNT (3)]
IWERK [CHAR (4)]
INGRP [CHAR (3)]

T087I
MANDT [CLNT (3)]
IZWEK [CHAR (2)]

T087K
MANDT [CLNT (3)]
UMWKZ [CHAR (5)]

T352R
MANDT [CLNT (3)]
IWERK [CHAR (4)]
REVRN [CHAR (8)]

T353I
MANDT [CLNT (3)]
ILART [CHAR (3)]

T356
MANDT [CLNT (3)]
ARTPR [CHAR (2)]
PRIOK [CHAR (1)]

T356A
MANDT [CLNT (3)]
ARTPR [CHAR (2)]

T357
MANDT [CLNT (3)]
WERKS [CHAR (4)]
BEBER [CHAR (3)]

T357M
MANDT [CLNT (3)]
ANLZU [CHAR (1)]

T370C
MANDT [CLNT (3)]
ABCKZ [CHAR (1)]

T399I
MANDT [CLNT (3)]
IWERK [CHAR (4)]

T411
MANDT [CLNT (3)]
VERWE [CHAR (3)]

T415S
MANDT [CLNT (3)]
STLST [NUMC (2)]

T416
MANDT [CLNT (3)]
STLAN [CHAR (1)]

T436A
MANDT [CLNT (3)]
WERKS [CHAR (4)]
FHORI [CHAR (3)]

T441R
MANDT [CLNT (3)]
PRREG [CHAR (2)]

T482
MANDT [CLNT (3)]
TERMKZ [CHAR (1)]

T499S
MANDT [CLNT (3)]
WERKS [CHAR (4)]
STAND [CHAR (10)]

T681A
MANDT [CLNT (3)]
KAPPL [CHAR (2)]

T681V
MANDT [CLNT (3)]
KVEWE [CHAR (1)]

T683
MANDT [CLNT (3)]
KVEWE [CHAR (1)]
KAPPL [CHAR (2)]
KALSM [CHAR (6)]

T778P
MANDT [CLNT (3)]
PLVAR [CHAR (2)]

T8J6A
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
CLASS [CHAR (3)]

T8J6C
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
CLASS [CHAR (3)]
SUBCLASS [CHAR (5)]

T8JG
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
VNAME [CHAR (6)]
ETYPE [CHAR (3)]
EDATE [NUMC (8)]

T8JJ
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
RECID [CHAR (2)]

T8JV
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
VNAME [CHAR (6)]

TAI5
MANDT [CLNT (3)]
SIZECL [CHAR (2)]

TAPRF
MANDT [CLNT (3)]
IVPRO [CHAR (6)]

TBMOT
MANDT [CLNT (3)]
BEMOT [CHAR (2)]

TC36
MANDT [CLNT (3)]
VERSN [NUMC (2)]

TCA01
MANDT [CLNT (3)]
PLNTY [CHAR (1)]

TCA09
MANDT [CLNT (3)]
PLNAW [CHAR (1)]

TCK03
MANDT [CLNT (3)]
KIVAR [CHAR (4)]

TCN41
MANDT [CLNT (3)]
PLNAW [CHAR (1)]
PROFIDNETZ [CHAR (7)]

TCO43
MANDT [CLNT (3)]
WERKS [CHAR (4)]
CO_PRODPRF [CHAR (6)]

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

TFACD
IDENT [CHAR (2)]

TFKB
MANDT [CLNT (3)]
FKBER [CHAR (16)]

TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]

TJ20
MANDT [CLNT (3)]
STMSA [CHAR (8)]

TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]

TKKAA
MANDT [CLNT (3)]
ABGSL [CHAR (6)]

TKO08
CLIENT [CLNT (3)]
KOKRS [CHAR (4)]
ABKRS [NUMC (2)]

TKV01
MANDT [CLNT (3)]
AWOBA [CHAR (2)]
AWLSL [CHAR (6)]

TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]

TTXJ
MANDT [CLNT (3)]
KALSM [CHAR (6)]
TXJCD [CHAR (