

SAP ABAP table EAM_S_IFLO_HIER_STRUC {IFLO Data and STRNO}

EAM_S_IFLO_HIER_STRUC	
MANDT	[CLNT (3)]
SPRAS	[LANG (1)]
MLANG	[LANG (1)]
TPLKZ	[CHAR (5)]
FLTYP	[CHAR (1)]
TPLMA	[CHAR (30)]
BEGRU	[CHAR (4)]
TRPNR	[CHAR (30)]
SUBMT	[CHAR (18)]
IWERK	[CHAR (4)]
INGRP	[CHAR (3)]
LGWID	[NUMC (8)]
RBNR	[CHAR (9)]
OBJNR	[CHAR (22)]
EQART	[CHAR (10)]
GEWEI	[UNIT (3)]
WAERS	[CUKY (5)]
HERLD	[CHAR (3)]
ABCKZ	[CHAR (1)]
SWERK	[CHAR (4)]
STORT	[CHAR (10)]
BEBER	[CHAR (3)]
PPSID	[NUMC (8)]
GSBER	[CHAR (4)]
KOKRS	[CHAR (4)]
KOSTL	[CHAR (10)]
PROID	[NUMC (8)]
BUKRS	[CHAR (4)]
ANLNR	[CHAR (12)]
ANLUN	[CHAR (4)]
DAUFN	[CHAR (12)]
AUFNR	[CHAR (12)]
VKORG	[CHAR (4)]
VTWEG	[CHAR (2)]
SPART	[CHAR (2)]
ADRNR	[CHAR (10)]
VKBUR	[CHAR (4)]
VKGRP	[CHAR (3)]
IFLOT_SNTYPE	[CHAR (2)]

EAM_S_IFLO_HIER_STRUC-ADRNR = ADRC-ADDRNUMBER

ADRC
<u>CLIENT</u> [CLNT (3)]
ADDRNUMBER [CHAR (10)]
DATE_FROM [DATS (8)]
<u>NATION</u> [CHAR (1)]

EAM_S_IFLO_HIER_STRUC-ANLUN = ANLA-ANLN2

ANLA
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
<u>ANLN1</u> [CHAR (12)]
ANLN2 [CHAR (4)]

EAM_S_IFLO_HIER_STRUC-ANLNR = ANLH-ANLN1

ANLH
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
<u>ANLN1</u> [CHAR (12)]

EAM_S_IFLO_HIER_STRUC-AUFNR = AUFK-AUFNR

AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

EAM_S_IFLO_HIER_STRUC-DAUFN = AUFK-AUFNR

EAM_S_IFLO_HIER_STRUC-LGWID = CRID-OBJID

CRID
MANDT [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]

EAM_S_IFLO_HIER_STRUC-PPSID = CRID-OBJID

EAM_S_IFLO_HIER_STRUC-KOSTL = CSKS-KOSTL

CSKS
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]

EAM_S_IFLO_HIER_STRUC-TPLMA = IFLOT-TPLNR

IFLOT
MANDT [CLNT (3)]
TPLNR [CHAR (30)]

EAM_S_IFLO_HIER_STRUC-TRPNR = IRLOT-TRPNR

IRLOT
MANDT [CLNT (3)]
TRPNR [CHAR (30)]

EAM_S_IFLO_HIER_STRUC-SUBMT = MARA-MATNR

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

EAM_S_IFLO_HIER_STRUC-OBJNR = ONR00-OBJNR

ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]

EAM_S_IFLO_HIER_STRUC-PROID = PRPS-PSPNR

PRPS
MANDT [CLNT (3)]
PSPNR [NUMC (8)]

EAM_S_IFLO_HIER_STRUC-MANDT = T000-MANDT

T000
MANDT [CLNT (3)]

EAM_S_IFLO_HIER_STRUC-BUKRS = T001-BUKRS

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

EAM_S_IFLO_HIER_STRUC-SWERK = T001W-WERKS

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

EAM_S_IFLO_HIER_STRUC-MLANG = T002-SPRAS

T002
SPRAS [LANG (1)]

EAM_S_IFLO_HIER_STRUC-SPRAS = T002-SPRAS

T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]

EAM_S_IFLO_HIER_STRUC-HERLD = T005-LAND1

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

EAM_S_IFLO_HIER_STRUC-GEWEI = T006-MSEHI

EAM_S_IFLO_HIER_STRUC-INGRP = T024I-INGRP

T024I
MANDT [CLNT (3)]
IWERK [CHAR (4)]
INGRP [CHAR (3)]

EAM_S_IFLO_HIER_STRUC-RBNR = T352B-RBNR

T352B
MANDT [CLNT (3)]
RBNR [CHAR (9)]

EAM_S_IFLO_HIER_STRUC-BEBER = T357-BEBER

T357
MANDT [CLNT (3)]
WERKS [CHAR (4)]
BEBER [CHAR (3)]

EAM_S_IFLO_HIER_STRUC-BEGRU = T370B-BEGRU

T370B
MANDT [CLNT (3)]
BEGRU [CHAR (4)]

EAM_S_IFLO_HIER_STRUC-ABCKZ = T370C-ABCKZ

T370C
MANDT [CLNT (3)]
ABCKZ [CHAR (1)]

EAM_S_IFLO_HIER_STRUC-FLTYP = T370F-FLTYP

T370F
MANDT [CLNT (3)]
FLTYP [CHAR (1)]

EAM_S_IFLO_HIER_STRUC-EQART = T370K-EQART

T370K
MANDT [CLNT (3)]
EQART [CHAR (10)]

EAM_S_IFLO_HIER_STRUC-TPLKZ = T370S-TPLKZ

T370S
MANDT [CLNT (3)]
TPLKZ [CHAR (5)]

EAM_S_IFLO_HIER_STRUC-IWERK = T399I-IWERK

T399I
MANDT [CLNT (3)]
IWERK [CHAR (4)]

EAM_S_IFLO_HIER_STRUC-STORT = T499S-STAND

T499S
MANDT [CLNT (3)]
WERKS [CHAR (4)]
STAND [CHAR (10)]

EAM_S_IFLO_HIER_STRUC-WAERS = TCURC-WAERS

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

EAM_S_IFLO_HIER_STRUC-GSBER = TGSB-GSBER

TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]

EAM_S_IFLO_HIER_STRUC-KOKRS = TKA01-KOKRS

TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]

EAM_S_IFLO_HIER_STRUC-IFLOT_SNTYPE = TQ80-QMART

TQ80
MANDT [CLNT (3)]
QMART [CHAR (2)]

EAM_S_IFLO_HIER_STRUC-VKGRP = TVBVK-VKGRP

TVBVK
MANDT [CLNT (3)]
VKBUR [CHAR (4)]
VKGRP [CHAR (3)]

EAM_S_IFLO_HIER_STRUC-VKBUR = TVKBZ-VKBUR

TVKBZ
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]
VKBUR [CHAR (4)]

EAM_S_IFLO_HIER_STRUC-VKORG = TVKO-VKORG

TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]

EAM_S_IFLO_HIER_STRUC-VTWEG = TVKOV-VTWEG

TVKOV
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]

EAM_S_IFLO_HIER_STRUC-SPART = TVTA-SPART

TVTA
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]