

SAP ABAP table EAML_V_NWM_OL {Generated Table for View}

EAML_V_NWM_OL-EQKANT = EQUI-EQUNR

EAML_V_NWM_OL
<u>MANDT</u> [CLNT (3)]
<u>KANXT</u> [CHAR (40)]
<u>SPRAS</u> [LANG (1)]
<u>KANTE</u> [CHAR (18)]
<u>NETID</u> [CHAR (8)]
<u>TPVON</u> [CHAR (30)]
<u>EQVON</u> [CHAR (18)]
<u>TPNACH</u> [CHAR (30)]
<u>EQNACH</u> [CHAR (18)]
<u>TPKANT</u> [CHAR (30)]
<u>EQKANT</u> [CHAR (18)]
<u>BEGRU</u> [CHAR (4)]

EQUI
<u>MANDT</u> [CLNT (3)]
<u>EQUNR</u> [CHAR (18)]

IFLOT
<u>MANDT</u> [CLNT (3)]
<u>TPLNR</u> [CHAR (30)]

T000
<u>MANDT</u> [CLNT (3)]

T002
<u>SPRAS</u> [LANG (1)]

T370B
<u>MANDT</u> [CLNT (3)]
<u>BEGRU</u> [CHAR (4)]

T372I
<u>MANDT</u> [CLNT (3)]
<u>NETID</u> [CHAR (8)]

{0,1} EAML_V_NWM_OL-EQNACH = EQUI-EQUNR 0..N

{0,1} EAML_V_NWM_OL-EQVON = EQUI-EQUNR 0..N

{0,1} EAML_V_NWM_OL-TPKANT = IFLOT-TPLNR 0..N

{0,1} EAML_V_NWM_OL-TPNACH = IFLOT-TPLNR 0..N

{0,1} EAML_V_NWM_OL-TPVON = IFLOT-TPLNR 0..N

1 EAML_V_NWM_OL-MANDT = T000-MANDT 0..N

1 EAML_V_NWM_OL-SPRAS = T002-SPRAS 0..N

{0,1} EAML_V_NWM_OL-BEGRU = T370B-BEGRU 0..N

{0,1} EAML_V_NWM_OL-NETID = T372I-NETID 0..N