

SAP ABAP table EAMS\_S\_BO\_WCM\_WAP\_HEADER {Business Object Work Approval - Header}

EAMS\_S\_BO\_WCM\_WAP\_HEADER-AUFNT = AUFK-AUFNR

0..N

<b>AUFK</b>
<i>MANDT</i> [CLNT (3)]
AUFNR [CHAR (12)]

EAMS\_S\_BO\_WCM\_WAP\_HEADER-WKCRID = CRID-OBJID

0..N

<b>CRID</b>
<i>MANDT</i> [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]

EAMS\_S\_BO\_WCM\_WAP\_HEADER-WKCRTP = CRID-OBJTY

0..N

<b>EQUI</b>
<i>MANDT</i> [CLNT (3)]
EQUNR [CHAR (18)]

EAMS\_S\_BO\_WCM\_WAP\_HEADER-EQUNR = EQUI-EQUNR

0..N

<b>IFLOT</b>
<i>MANDT</i> [CLNT (3)]
TPLNR [CHAR (30)]

EAMS\_S\_BO\_WCM\_WAP\_HEADER-TPLNR = IFLOT-TPLNR

EAMS\_S\_BO\_WCM\_WAP\_HEADER-OBJNR = ONR00-OBJNR

0..N

<b>ONR00</b>
<i>MANDT</i> [CLNT (3)]
OBJNR [CHAR (22)]

EAMS\_S\_BO\_WCM\_WAP\_HEADER-PSPEL = PRPS-PSPNR

0..N

<b>PRPS</b>
<i>MANDT</i> [CLNT (3)]
PSPNR [NUMC (8)]

EAMS\_S\_BO\_WCM\_WAP\_HEADER-MANDT = T000-MANDT

0..N

<b>T000</b>
<i>MANDT</i> [CLNT (3)]

EAMS\_S\_BO\_WCM\_WAP\_HEADER-RCUNIT = T006-MSEHI

0..N

<b>T006</b>
<i>MANDT</i> [CLNT (3)]
MSEHI [UNIT (3)]

EAMS\_S\_BO\_WCM\_WAP\_HEADER-INGRP = T024I-INGRP

0..N

<b>T024I</b>
<i>MANDT</i> [CLNT (3)]
<i>IWERK</i> [CHAR (4)]
INGRP [CHAR (3)]

EAMS\_S\_BO\_WCM\_WAP\_HEADER-PRIOK = T356-PRIOK

0..N

<b>T356</b>
<i>MANDT</i> [CLNT (3)]
<i>ARTPR</i> [CHAR (2)]
PRIOK [CHAR (1)]

EAMS\_S\_BO\_WCM\_WAP\_HEADER-BEGRU = T370B-BEGRU

0..N

<b>T370B</b>
<i>MANDT</i> [CLNT (3)]
BEGRU [CHAR (4)]

EAMS\_S\_BO\_WCM\_WAP\_HEADER-IWERK = T399I-IWERK

0..N

<b>T399I</b>
<i>MANDT</i> [CLNT (3)]
<i>IWERK</i> [CHAR (4)]

EAMS\_S\_BO\_WCM\_WAP\_HEADER-WAPSTSMA = TJ20-STSMA

0..N

<b>TJ20</b>
<i>MANDT</i> [CLNT (3)]
STSMA [CHAR (8)]

EAMS\_S\_BO\_WCM\_WAP\_HEADER-ETAPE = WCCF-ETAPE

0..N

<b>WCCF</b>
<i>MANDT</i> [CLNT (3)]
<i>IWERK</i> [CHAR (4)]
ETAPE [CHAR (20)]

EAMS\_S\_BO\_WCM\_WAP\_HEADER-ANLZU = WCCG-ANLZU

0..N

<b>WCCG</b>
<i>MANDT</i> [CLNT (3)]
<i>IWERK</i> [CHAR (4)]
ANLZU [CHAR (2)]

EAMS\_S\_BO\_WCM\_WAP\_HEADER-TRAIN = WCCH-TRAIN

0..N

<b>WCCH</b>
<i>MANDT</i> [CLNT (3)]
<i>IWERK</i> [CHAR (4)]
TRAIN [CHAR (3)]

EAMS\_S\_BO\_WCM\_WAP\_HEADER-WAPUSE = WCCX-WAPUSE

0..N

<b>WCCX</b>
<i>MANDT</i> [CLNT (3)]
<i>IWERK</i> [CHAR (4)]
WAPUSE [CHAR (3)]

<b>EAMS_S_BO_WCM_WAP_HEADER</b>
<i>MANDT</i> [CLNT (3)]
OBJNR [CHAR (22)]
WAPUSE [CHAR (3)]
INGRP [CHAR (3)]
IWERK [CHAR (4)]
WKCRTP [CHAR (2)]
WKCRID [NUMC (8)]
BEGRU [CHAR (4)]
ANLZU [CHAR (2)]
RCUNIT [UNIT (3)]
PRIOK [CHAR (1)]
TPLNR [CHAR (30)]
EQUNR [CHAR (18)]
TRAIN [CHAR (3)]
PSPEL [NUMC (8)]
AUFNT [CHAR (12)]
ETAPE [CHAR (20)]
WAPSTSMA [CHAR (8)]

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N