

SAP ABAP table EAMS_S_NAV_PR_ID_ATTR {NAV - Purchase Requisition attributes}

EAMS_S_NAV_PR_ID_ATTR
MANDT [CLNT (3)]
BSART [CHAR (4)]
FRGKZ [CHAR (1)]
EKGRP [CHAR (3)]
MATNR [CHAR (18)]
EMATN [CHAR (18)]
WERKS [CHAR (4)]
LGORT [CHAR (4)]
MATKL [CHAR (9)]
MEINS [UNIT (3)]
LPEIN [CHAR (1)]
PSTYP [CHAR (1)]
KNTTP [CHAR (1)]
LIFNR [CHAR (10)]
FLIEF [CHAR (10)]
EKORG [CHAR (4)]
KONNR [CHAR (10)]
KTPNR [NUMC (5)]
INFNR [CHAR (10)]
DISPO [CHAR (3)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]
LBLNI [CHAR (10)]
BWTAR [CHAR (10)]
SOBKZ [CHAR (1)]
BMEIN [UNIT (3)]
PACKNO [NUMC (10)]
FRGGR [CHAR (2)]
AKTNR [CHAR (10)]
ADRNR [CHAR (10)]
ADRNR2 [CHAR (10)]
KUNNR [CHAR (10)]
EMLIF [CHAR (10)]
WAERS [CUKY (5)]
SPRAS [LANG (1)]
MFRNR [CHAR (10)]
BESWK [CHAR (4)]
PRIO_URG [NUMC (2)]
PRIO_REQ [NUMC (3)]
ADVCODE [CHAR (2)]
STACODE [CHAR (2)]

0..N10..N11

EAMS_S_NAV_PR_ID_ATTR-ADVCODE = /ISDFPS/ADVCODE2-ADVCODE

_ISDFPS_ADVCODE2
MANDT [CLNT (3)]
BSART [CHAR (4)]
ADVCODE [CHAR (2)]

EAMS_S_NAV_PR_ID_ATTR-STACODE = /ISDFPS/CSTACODE-STACODE

_ISDFPS_CSTACODE
MANDT [CLNT (3)]
STACODE [CHAR (2)]

EAMS_S_NAV_PR_ID_ATTR-ADRN2 = ADRC-ADDRNUMBER

ADRC
CLIENT [CLNT (3)]
ADDRNUMBER [CHAR (10)]
DATE_FROM [DATS (8)]
NATION [CHAR (1)]

EAMS_S_NAV_PR_ID_ATTR-ADRN2 = ADRC-ADDRNUMBER

ADRC
CLIENT [CLNT (3)]
ADDRNUMBER [CHAR (10)]
DATE_FROM [DATS (8)]
NATION [CHAR (1)]

EAMS_S_NAV_PR_ID_ATTR-INFNR = EINA-INFNR

EINA
MANDT [CLNT (3)]
INFNR [CHAR (10)]

EAMS_S_NAV_PR_ID_ATTR-EBELN = EKKO-EBELN

EKKO
MANDT [CLNT (3)]
EBELN [CHAR (10)]

EAMS_S_NAV_PR_ID_ATTR-KONNR = EKKO-EBELN

EKKO
MANDT [CLNT (3)]
EBELN [CHAR (10)]

EAMS_S_NAV_PR_ID_ATTR-EBELP = EKPO-EBELP

EKPO
MANDT [CLNT (3)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]

EAMS_S_NAV_PR_ID_ATTR-KTPNR = EKPO-EBELP

EKPO
MANDT [CLNT (3)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]

EAMS_S_NAV_PR_ID_ATTR-PACKNO = ESLH-PACKNO

ESLH
MANDT [CLNT (3)]
PACKNO [NUMC (10)]

EAMS_S_NAV_PR_ID_ATTR-LBLNI = ESSR-LBLNI

ESSR
MANDT [CLNT (3)]
LBLNI [CHAR (10)]

EAMS_S_NAV_PR_ID_ATTR-KUNNR = KNA1-KUNNR

KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]

EAMS_S_NAV_PR_ID_ATTR-EMLIF = LFA1-LIFNR

LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]

EAMS_S_NAV_PR_ID_ATTR-FLIEF = LFA1-LIFNR

LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]

EAMS_S_NAV_PR_ID_ATTR-LIFNR = LFA1-LIFNR

LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]

EAMS_S_NAV_PR_ID_ATTR-MFRNR = LFA1-LIFNR

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

EAMS_S_NAV_PR_ID_ATTR-EMATN = MARA-MATNR

PREQ
MANDT [CLNT (3)]
PRIO_REQ [NUMC (3)]

EAMS_S_NAV_PR_ID_ATTR-MATNR = MARA-MATNR

PREQ
MANDT [CLNT (3)]
PRIO_REQ [NUMC (3)]

EAMS_S_NAV_PR_ID_ATTR-PRIO_REQ = PREQ-PRIO_REQ

PURG
MANDT [CLNT (3)]
PRIO_URG [NUMC (2)]

EAMS_S_NAV_PR_ID_ATTR-PRIO_URG = PURG-PRIO_URG

PURG
MANDT [CLNT (3)]
PRIO_URG [NUMC (2)]

EAMS_S_NAV_PR_ID_ATTR-MANDT = T000-MANDT

T000
MANDT [CLNT (3)]

EAMS_S_NAV_PR_ID_ATTR-LGORT = T001L-LGORT

T001L
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LGORT [CHAR (4)]

EAMS_S_NAV_PR_ID_ATTR-BESWK = T001W-WERKS

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

EAMS_S_NAV_PR_ID_ATTR-WERKS = T001W-WERKS

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

EAMS_S_NAV_PR_ID_ATTR-SPRAS = T002-SPRAS

T002
SPRAS [LANG (1)]

EAMS_S_NAV_PR_ID_ATTR-BMEIN = T006-MSEHI

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

EAMS_S_NAV_PR_ID_ATTR-MEINS = T006-MSEHI

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

EAMS_S_NAV_PR_ID_ATTR-MATKL = T023-MATKL

T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]

EAMS_S_NAV_PR_ID_ATTR-EKGRP = T024-EKGRP

T024
MANDT [CLNT (3)]
EKGRP [CHAR (3)]

EAMS_S_NAV_PR_ID_ATTR-DISPO = T024D-DISPO

T024D
MANDT [CLNT (3)]
WERKS [CHAR (4)]
DISPO [CHAR (3)]

EAMS_S_NAV_PR_ID_ATTR-EKORG = T024E-EKORG

T024E
MANDT [CLNT (3)]
EKORG [CHAR (4)]

EAMS_S_NAV_PR_ID_ATTR-SOBKZ = T148-SOBKZ

T148
MANDT [CLNT (3)]
SOBKZ [CHAR (1)]

EAMS_S_NAV_PR_ID_ATTR-BWTAR = T149D-BWTAR

T149D
MANDT [CLNT (3)]
BWTAR [CHAR (10)]

EAMS_S_NAV_PR_ID_ATTR-BSART = T161-BSART

T161
MANDT [CLNT (3)]
BSART [CHAR (4)]

EAMS_S_NAV_PR_ID_ATTR-FRGKZ = T161S-FRGKZ

T161S
MANDT [CLNT (3)]
FRGKZ [CHAR (1)]

EAMS_S_NAV_PR_ID_ATTR-PSTYP = T163-PSTYP

T163
MANDT [CLNT (3)]
PSTYP [CHAR (1)]

EAMS_S_NAV_PR_ID_ATTR-KNTTP = T163K-KNTTP

T163K
MANDT [CLNT (3)]
KNTTP [CHAR (1)]

EAMS_S_NAV_PR_ID_ATTR-FRGGR = T16FG-FRGGR

T16FG
MANDT [CLNT (3)]
FRGGR [CHAR (2)]

EAMS_S_NAV_PR_ID_ATTR-WAERS = TCURC-WAERS

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

EAMS_S_NAV_PR_ID_ATTR-LPEIN = TPRG-PRGBZ

TPRG
MANDT [CLNT (3)]
SPRAS [LANG (1)]
PRGBZ [CHAR (1)]

EAMS_S_NAV_PR_ID_ATTR-AKTNR = WAKH-AKTNR

WAKH
MANDT [CLNT (3)]
AKTNR [CHAR (10)]