

SAP ABAP table EHSWAV_ENTAM {Generated Table for View}

EHSWAV_ENTAM-EANOCAT = EHSWAC_EANOCAT-EANOCAT

EHSWAC_EANOCAT
<u>MANDT</u> [CLNT (3)]
EANOCAT [CHAR (6)]

LAGP
<u>MANDT</u> [CLNT (3)]
<u>LGNUM</u> [CHAR (3)]
<u>LGTYP</u> [CHAR (3)]
LGPLA [CHAR (10)]

MARA
<u>MANDT</u> [CLNT (3)]
<u>MATNR</u> [CHAR (18)]

T001
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]

T001L
<u>MANDT</u> [CLNT (3)]
<u>WERKS</u> [CHAR (4)]
<u>LGORT</u> [CHAR (4)]

T001W
<u>MANDT</u> [CLNT (3)]
<u>WERKS</u> [CHAR (4)]

T006
<u>MANDT</u> [CLNT (3)]
<u>MSEHI</u> [UNIT (3)]

T300
<u>MANDT</u> [CLNT (3)]
<u>LGNUM</u> [CHAR (3)]

T301
<u>MANDT</u> [CLNT (3)]
<u>LGNUM</u> [CHAR (3)]
<u>LGTYP</u> [CHAR (3)]

TGSB
<u>MANDT</u> [CLNT (3)]
<u>GSBER</u> [CHAR (4)]

EHSWAV_ENTAM
<u>MANDT</u> [CLNT (3)]
<u>RECN</u> [CHAR (32)]
EANOCAT [CHAR (6)]
MATNR [CHAR (18)]
EAINTAMU [UNIT (3)]
EAEXTAMU [UNIT (3)]
WERKSS [CHAR (4)]
LGORT [CHAR (4)]
LGNUM [CHAR (3)]
LGTYP [CHAR (3)]
LGPLA [CHAR (10)]
BUKRS [CHAR (4)]
WERKS [CHAR (4)]
GSBER [CHAR (4)]
MATNRO [CHAR (18)]

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

EHSWAV_ENTAM-LGPLA = LAGP-LGPLA

EHSWAV_ENTAM-MATNR = MARA-MATNR

EHSWAV_ENTAM-MATNRO = MARA-MATNR

EHSWAV_ENTAM-BUKRS = T001-BUKRS

EHSWAV_ENTAM-LGORT = T001L-LGORT

EHSWAV_ENTAM-WERKS = T001W-WERKS

EHSWAV_ENTAM-WERKSS = T001W-WERKS

EHSWAV_ENTAM-EAEXTAMU = T006-MSEHI

EHSWAV_ENTAM-EAINTAMU = T006-MSEHI

EHSWAV_ENTAM-LGNUM = T300-LGNUM

EHSWAV_ENTAM-LGTYP = T301-LGTYP

EHSWAV_ENTAM-GSBER = TGSB-GSBER