

SAP ABAP table EMLGN {Data Division MLGN}

EMLGN-BEZME = T006-MSEHI

EMLGN
<i>LGBKZ</i> [CHAR (3)]
<i>LTKZE</i> [CHAR (3)]
<i>LTKZA</i> [CHAR (3)]
<i>LHME1</i> [UNIT (3)]
<i>LHME2</i> [UNIT (3)]
<i>LHME3</i> [UNIT (3)]
<i>LETY1</i> [CHAR (3)]
<i>LETY2</i> [CHAR (3)]
<i>LETY3</i> [CHAR (3)]
<i>LVSME</i> [UNIT (3)]
<i>BLOCK</i> [CHAR (2)]
<i>BSSKZ</i> [CHAR (1)]
<i>BEZME</i> [UNIT (3)]
<i>PLKPT</i> [CHAR (3)]

EMLGN-LHME1 = T006-MSEHI

EMLGN-LHME2 = T006-MSEHI

EMLGN-LHME3 = T006-MSEHI

EMLGN-LVSME = T006-MSEHI

EMLGN-PLKPT = T301-LGTYP

EMLGN-LGBKZ = T304-LGBKZ

EMLGN-LTKZA = T305-LGTKZ

EMLGN-LTKZE = T305-LGTKZ

EMLGN-BSSKZ = T306-BSSKZ

EMLGN-LETY1 = T307-LETYP

EMLGN-LETY2 = T307-LETYP

EMLGN-LETY3 = T307-LETYP

EMLGN-BLOCK = T338-BLOCK

T006
<i>MANDT</i> [CLNT (3)]
<i>MSEHI</i> [UNIT (3)]

T301
<i>MANDT</i> [CLNT (3)]
<i>LGNUM</i> [CHAR (3)]
<i>LGTP</i> [CHAR (3)]

T304
<i>MANDT</i> [CLNT (3)]
<i>LGNUM</i> [CHAR (3)]
<i>LGBKZ</i> [CHAR (3)]

T305
<i>MANDT</i> [CLNT (3)]
<i>LGNUM</i> [CHAR (3)]
<i>LGTKZ</i> [CHAR (3)]

T306
<i>MANDT</i> [CLNT (3)]
<i>LGNUM</i> [CHAR (3)]
<i>BSSKZ</i> [CHAR (1)]

T307
<i>MANDT</i> [CLNT (3)]
<i>LGNUM</i> [CHAR (3)]
<i>LETYP</i> [CHAR (3)]

T338
<i>MANDT</i> [CLNT (3)]
<i>LGNUM</i> [CHAR (3)]
<i>BLOCK</i> [CHAR (2)]