

SAP ABAP table FKKOPLST {Document: Displayable Fields (Business Partner Items)}

FKKOPLST-EMGPA = BUT000-PARTNER

BUT000
<u>CLIENT</u> [CLNT (3)]
PARTNER [CHAR (10)]

FKKOPLST-GPART = BUT000-PARTNER

BUT0BK
<u>MANDT</u> [CLNT (3)]
<u>PARTNER</u> [CHAR (10)]
BKVID [CHAR (4)]

FKKOPLST-EMBVT = BUT0BK-BKVID

FAGL_SEGM
<u>MANDT</u> [CLNT (3)]
SEGMENT [CHAR (10)]

FKKOPLST-SEGMENT = FAGL_SEGM-SEGMENT

FKKVK
<u>MANDT</u> [CLNT (3)]
VKONT [CHAR (12)]

FKKOPLST-VKONT = FKKVK-VKONT

J_1BBRANCH
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]
BRANCH [CHAR (4)]

FKKOPLST-BUPLA = J_1BBRANCH-BRANCH

SKA1
<u>MANDT</u> [CLNT (3)]
<u>KTOPL</u> [CHAR (4)]
SAKNR [CHAR (10)]

FKKOPLST-HKONT = SKA1-SAKNR

T001
<u>MANDT</u> [CLNT (3)]
BUKRS [CHAR (4)]

FKKOPLST-MWSKO = SKA1-SAKNR

T005
<u>MANDT</u> [CLNT (3)]
<u>LAND1</u> [CHAR (3)]

FKKOPLST-MWVKO = SKA1-SAKNR

T007A
<u>MANDT</u> [CLNT (3)]
<u>KALSM</u> [CHAR (6)]
MWSKZ [CHAR (2)]

FKKOPLST-BUKRS = T001-BUKRS

T035
<u>MANDT</u> [CLNT (3)]
GRUPP [CHAR (10)]

FKKOPLST-PYBUK = T001-BUKRS

T036
<u>MANDT</u> [CLNT (3)]
<u>EBENE</u> [CHAR (2)]

FKKOPLST-LANDL = T005-LAND1

T059Q
<u>MANDT</u> [CLNT (3)]
<u>LAND1</u> [CHAR (3)]
<u>QSSKZ</u> [CHAR (2)]

FKKOPLST-MWSKZ = T007A-MWSKZ

T880
<u>MANDT</u> [CLNT (3)]
<u>RCOMP</u> [CHAR (6)]

FKKOPLST-FDGRP = T035-GRUPP

TCURC
<u>MANDT</u> [CLNT (3)]
<u>WAERS</u> [CUKY (5)]

FKKOPLST-FDLEV = T036-EBENE

TFK000K
KONTT [CHAR (2)]

FKKOPLST-QSSKZ = T059Q-QSSKZ

TFK000S
<u>MANDT</u> [CLNT (3)]
SPPOS [CHAR (1)]

FKKOPLST-VBUND = T880-RCOMP

TFK001A
AUGRD [CHAR (2)]

FKKOPLST-WAERS = TCURC-WAERS

TFK001P
<u>MANDT</u> [CLNT (3)]
<u>PERSL</u> [CHAR (4)]

FKKOPLST-KONTT = TFK000K-KONTT

TFK003
<u>MANDT</u> [CLNT (3)]
<u>APPLK</u> [CHAR (1)]
<u>BLART</u> [CHAR (2)]

FKKOPLST-CLRLO = TFK000S-SPPOS

TFK007F
<u>MANDT</u> [CLNT (3)]
<u>LAND</u> [CHAR (3)]
<u>STRKZ</u> [CHAR (2)]

FKKOPLST-AUGRD = TFK001A-AUGRD

TFK008
<u>MANDT</u> [CLNT (3)]
<u>ZAHL</u> [CHAR (1)]
<u>STRKZ</u> [CHAR (2)]

FKKOPLST-PERSL = TFK001P-PERSL

TFK047A
<u>MANDT</u> [CLNT (3)]
MAHNV [CHAR (2)]

FKKOPLST-BLART = TFK003-BLART

TFK047S
<u>MANDT</u> [CLNT (3)]
<u>MANSP</u> [CHAR (1)]

FKKOPLST-STRKZ = TFK007F-STRKZ

TFK056A
<u>MANDT</u> [CLNT (3)]
<u>IKEY</u> [CHAR (2)]

FKKOPLST-SPZAH = TFK008-ZAHL

TFK056S
<u>MANDT</u> [CLNT (3)]
<u>SPERZ</u> [CHAR (1)]

FKKOPLST-MAHNV = TFK047A-MAHNV

TFKHVO
<u>MANDT</u> [CLNT (3)]
<u>APPLK</u> [CHAR (1)]
<u>HVORG</u> [CHAR (4)]

FKKOPLST-MANSP = TFK047S-MANSP

TFKTVO
<u>MANDT</u> [CLNT (3)]
<u>APPLK</u> [CHAR (1)]
<u>HVORG</u> [CHAR (4)]
<u>TVORG</u> [CHAR (4)]

FKKOPLST-IKEY = TFK056A-IKEY

TGSB
<u>MANDT</u> [CLNT (3)]
<u>GSBER</u> [CHAR (4)]

FKKOPLST-SPERZ = TFK056S-SPERZ

TSPA
<u>MANDT</u> [CLNT (3)]
<u>SPART</u> [CHAR (2)]

FKKOPLST-HVORG = TFKHVO-HVORG

TTXJ
<u>MANDT</u> [CLNT (3)]
<u>KALSM</u> [CHAR (6)]
<u>TXJCD</u> [CHAR (15)]

FKKOPLST-TVORG = TFKTVO-TVORG

TGSB
<u>MANDT</u> [CLNT (3)]
<u>GSBER</u> [CHAR (4)]

FKKOPLST-GSBER = TGSB-GSBER

TSPA
<u>MANDT</u> [CLNT (3)]
<u>SPART</u> [CHAR (2)]

FKKOPLST-SPART = TSPA-SPART

TSPA
<u>MANDT</u> [CLNT (3)]
<u>SPART</u> [CHAR (2)]

FKKOPLST-TXJCD = TTXJ-TXJCD

TTXJ
<u>MANDT</u> [CLNT (3)]
<u>KALSM</u> [CHAR (6)]
<u>TXJCD</u> [CHAR (15)]

FKKOPLST
BUKRS [CHAR (4)]
GSBER [CHAR (4)]
BUPLA [CHAR (4)]
SEGMENT [CHAR (10)]
GPART [CHAR (10)]
VKONT [CHAR (12)]
HVORG [CHAR (4)]
TVORG [CHAR (4)]
SPART [CHAR (2)]
HKONT [CHAR (10)]
MWSKZ [CHAR (2)]
WAERS [CUKY (5)]
MWSKO [CHAR (10)]
MWVKO [CHAR (10)]
SPZAH [CHAR (1)]
PYBUK [CHAR (4)]
PERSL [CHAR (4)]
AUGRD [CHAR (2)]
MAHNV [CHAR (2)]
MANSP [CHAR (1)]
FDGRP [CHAR (10)]
FDLEV [CHAR (2)]
SPERZ [CHAR (1)]
TXJCD [CHAR (15)]
VBUND [CHAR (6)]
KONTT [CHAR (2)]
BLART [CHAR (2)]
EMGPA [CHAR (10)]
EMBVT [CHAR (4)]
IKEY [CHAR (2)]
QSSKZ [CHAR (2)]
STRKZ [CHAR (2)]
LANDL [CHAR (3)]
CLRLO [CHAR (1)]