

SAP ABAP table FKKZWFPOS {Items to be Adjusted}

FKKZWFPOS-EMGPA = BUT000-PARTNER

| BUT000                     |
|----------------------------|
| <u>CLIENT</u> [CLNT (3)]   |
| <u>PARTNER</u> [CHAR (10)] |

FKKZWFPOS-GPART = BUT000-PARTNER

| BUT0BK                     |
|----------------------------|
| <u>MANDT</u> [CLNT (3)]    |
| <u>PARTNER</u> [CHAR (10)] |
| <u>BKVID</u> [CHAR (4)]    |

FKKZWFPOS-EMBVT = BUT0BK-BKVID

FKKZWFPOS-SEGMENT = FAGL\_SEGM-SEGMENT

| FAGL_SEGM                  |
|----------------------------|
| <u>MANDT</u> [CLNT (3)]    |
| <u>SEGMENT</u> [CHAR (10)] |

FKKZWFPOS-VKONT = FKKVK-VKONT

| FKKVK                    |
|--------------------------|
| <u>MANDT</u> [CLNT (3)]  |
| <u>VKONT</u> [CHAR (12)] |

FKKZWFPOS-BUPLA = J\_1BBRANCH-BRANCH

| J_1BBRANCH               |
|--------------------------|
| <u>MANDT</u> [CLNT (3)]  |
| <u>BUKRS</u> [CHAR (4)]  |
| <u>BRANCH</u> [CHAR (4)] |

FKKZWFPOS-HKONT = SKA1-SAKNR

| SKA1                     |
|--------------------------|
| <u>MANDT</u> [CLNT (3)]  |
| <u>KTOPL</u> [CHAR (4)]  |
| <u>SAKNR</u> [CHAR (10)] |

FKKZWFPOS-MWSKO = SKA1-SAKNR

FKKZWFPOS-MWVKO = SKA1-SAKNR

FKKZWFPOS-BUKRS = T001-BUKRS

| T001                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>BUKRS</u> [CHAR (4)] |

FKKZWFPOS-PYBUK = T001-BUKRS

FKKZWFPOS-LANDL = T005-LAND1

| T005                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>LAND1</u> [CHAR (3)] |

FKKZWFPOS-MWSKZ = T007A-MWSKZ

| T007A                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>KALSM</u> [CHAR (6)] |
| <u>MWSKZ</u> [CHAR (2)] |

FKKZWFPOS-FDGRP = T035-GRUPP

| T035                     |
|--------------------------|
| <u>MANDT</u> [CLNT (3)]  |
| <u>GRUPP</u> [CHAR (10)] |

FKKZWFPOS-FDLEV = T036-EBENE

| T036                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>EBENE</u> [CHAR (2)] |

FKKZWFPOS-QSSKZ = T059Q-QSSKZ

| T059Q                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>LAND1</u> [CHAR (3)] |
| <u>QSSKZ</u> [CHAR (2)] |

FKKZWFPOS-VBUND = T880-RCOMP

FKKZWFPOS-WAERS = TCURC-WAERS

| T880                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>RCOMP</u> [CHAR (6)] |

FKKZWFPOS-KONTT = TFK000K-KONTT

| TCURC                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>WAERS</u> [CUKY (5)] |

FKKZWFPOS-AUGRD = TFK001A-AUGRD

FKKZWFPOS-PERSL = TFK001P-PERSL

| TFK000K                 |
|-------------------------|
| <u>KONTT</u> [CHAR (2)] |

| TFK001A                 |
|-------------------------|
| <u>AUGRD</u> [CHAR (2)] |

FKKZWFPOS-BLART = TFK003-BLART

FKKZWFPOS-STRKZ = TFK007F-STRKZ

| TFK001P                 |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>PERSL</u> [CHAR (4)] |

| TFK003                  |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>APPLK</u> [CHAR (1)] |
| <u>BLART</u> [CHAR (2)] |

FKKZWFPOS-SPZAH = TFK008-ZAHLS

FKKZWFPOS-MAHNV = TFK047A-MAHNV

FKKZWFPOS-MANSP = TFK047S-MANSP

FKKZWFPOS-IKEY = TFK056A-IKEY

FKKZWFPOS-SPERZ = TFK056S-SPERZ

FKKZWFPOS-HVORG = TFKHVO-HVORG

FKKZWFPOS-TVORG = TFKTVO-TVORG

FKKZWFPOS-GSBER = TGSB-GSBER

FKKZWFPOS-SPART = TSPA-SPART

FKKZWFPOS-TXJCD = TTXJ-TXJCD

| TFK007F                 |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>LAND</u> [CHAR (3)]  |
| <u>STRKZ</u> [CHAR (2)] |

| TFK008                  |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>ZAHLS</u> [CHAR (1)] |

| TFK047A                 |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>MAHNV</u> [CHAR (2)] |

| TFK047S                 |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>MANSP</u> [CHAR (1)] |

| TFK056A                 |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>IKEY</u> [CHAR (2)]  |

| TFK056S                 |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>SPERZ</u> [CHAR (1)] |

| TFKHVO                  |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>APPLK</u> [CHAR (1)] |
| <u>HVORG</u> [CHAR (4)] |

| TFKTVO                  |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>APPLK</u> [CHAR (1)] |
| <u>HVORG</u> [CHAR (4)] |
| <u>TVORG</u> [CHAR (4)] |

| TGSB                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>GSBER</u> [CHAR (4)] |

| TSPA                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>SPART</u> [CHAR (2)] |

| TTXJ                     |
|--------------------------|
| <u>MANDT</u> [CLNT (3)]  |
| <u>KALSM</u> [CHAR (6)]  |
| <u>TXJCD</u> [CHAR (15)] |

| FKKZWFPOS                  |
|----------------------------|
| <u>BUKRS</u> [CHAR (4)]    |
| <u>GSBER</u> [CHAR (4)]    |
| <u>BUPLA</u> [CHAR (4)]    |
| <u>SEGMENT</u> [CHAR (10)] |
| <u>GPART</u> [CHAR (10)]   |
| <u>VKONT</u> [CHAR (12)]   |
| <u>HVORG</u> [CHAR (4)]    |
| <u>TVORG</u> [CHAR (4)]    |
| <u>SPART</u> [CHAR (2)]    |
| <u>HKONT</u> [CHAR (10)]   |
| <u>MWSKZ</u> [CHAR (2)]    |
| <u>WAERS</u> [CUKY (5)]    |
| <u>MWSKO</u> [CHAR (10)]   |
| <u>MWVKO</u> [CHAR (10)]   |
| <u>SPZAH</u> [CHAR (1)]    |
| <u>PYBUK</u> [CHAR (4)]    |
| <u>PERSL</u> [CHAR (4)]    |
| <u>AUGRD</u> [CHAR (2)]    |
| <u>MAHNV</u> [CHAR (2)]    |
| <u>MANSP</u> [CHAR (1)]    |
| <u>FDGRP</u> [CHAR (10)]   |
| <u>FDLEV</u> [CHAR (2)]    |
| <u>SPERZ</u> [CHAR (1)]    |
| <u>TXJCD</u> [CHAR (15)]   |
| <u>VBUND</u> [CHAR (6)]    |
| <u>KONTT</u> [CHAR (2)]    |
| <u>BLART</u> [CHAR (2)]    |
| <u>EMGPA</u> [CHAR (10)]   |
| <u>EMBVT</u> [CHAR (4)]    |
| <u>IKEY</u> [CHAR (2)]     |
| <u>QSSKZ</u> [CHAR (2)]    |
| <u>STRKZ</u> [CHAR (2)]    |
| <u>LANDL</u> [CHAR (3)]    |