

SAP ABAP table FMLGD_H_CUST {Note to Payee Control}

FMLGD_H_CUST
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]
<u>VGTYPE</u> [CHAR (8)]
<u>VGINT</u> [CHAR (4)]
<u>VGEXT</u> [CHAR (27)]
<u>VOZPM</u> [CHAR (1)]
<u>VALTY</u> [NUMC (4)]
<u>VALFR</u> [CHAR (30)]
<u>VTYP1</u> [NUMC (2)]
<u>VTYP2</u> [NUMC (2)]
<u>GRPNR</u> [CHAR (2)]
<u>VGNEW</u> [CHAR (4)]

FMLGD_H_GRPNR
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]
<u>MAPPE</u> [CHAR (2)]

FMLGD_H_VALTYP
<u>MANDT</u> [CLNT (3)]
<u>VALTY</u> [NUMC (4)]

FMLGD_H_VTYPX
<u>VTYP1</u> [NUMC (2)]
<u>VTYP2</u> [NUMC (2)]
<u>FLAG</u> [CHAR (1)]

T028D
<u>MANDT</u> [CLNT (3)]
<u>VGINT</u> [CHAR (4)]

T028G
<u>MANDT</u> [CLNT (3)]
<u>VGTYPE</u> [CHAR (8)]
<u>VGEXT</u> [CHAR (27)]
<u>VOZPM</u> [CHAR (1)]

T028V
<u>MANDT</u> [CLNT (3)]
<u>VGTYPE</u> [CHAR (8)]

FMLGD_H_CUST-GRPNR = FMLGD_H_GRPNR-MAPPE 0..N

FMLGD_H_CUST-VALTY = FMLGD_H_VALTYP-VALTY 0..N

FMLGD_H_CUST-VTYP1 = FMLGD_H_VTYPX-VTYP1 0..N

FMLGD_H_CUST-VTYP2 = FMLGD_H_VTYPX-VTYP2 0..N

FMLGD_H_CUST-VGINT = T028D-VGINT 0..N

FMLGD_H_CUST-VGNEW = T028D-VGINT 0..N

FMLGD_H_CUST-VGEXT = T028G-VGEXT 0..N

FMLGD_H_CUST-VGTYPE = T028V-VGTYPE 0..N