

SAP ABAP table FPRL_ITEM {Item Data}

FPRL_ITEM
MANDT [CLNT (3)]
GUID [RAW (16)]
LIST_ID [NUMC (10)]
STATUS [CHAR (3)]
ALEVEL [NUMC (2)]
APPLIC [CHAR (10)]
BUKRS [CHAR (4)]
LIFNR [CHAR (10)]
KUNNR [CHAR (10)]
VBUND [CHAR (6)]
WAERS [CUKY (5)]
BLART [CHAR (2)]
BSCHL [CHAR (2)]
HKONT [CHAR (10)]
SAKNR [CHAR (10)]
UMSKZ [CHAR (1)]
GSBER [CHAR (4)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]
LZBKZ [CHAR (3)]
LANDL [CHAR (3)]
ZLSPR [CHAR (1)]
ZBUKR [CHAR (4)]
HBKID [CHAR (5)]
RZawe [CHAR (1)]
UZawe [CHAR (2)]

EKKO
MANDT [CLNT (3)]
EBELN [CHAR (10)]

EKPO
MANDT [CLNT (3)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]

FPRL_APPLIC
APPLICATION [CHAR (10)]

FPRL_HEADER
MANDT [CLNT (3)]
LIST_ID [NUMC (10)]

FPRL_ITEM_STAT
STATUS [CHAR (3)]

FPRL_LEVELS
MANDT [CLNT (3)]
APPLICATION [CHAR (10)]
ALEVEL [NUMC (2)]

KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]

LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]

SKB1
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
SAKNR [CHAR (10)]

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

T003
MANDT [CLNT (3)]
BLART [CHAR (2)]

T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]

T008
MANDT [CLNT (3)]
ZAHL1 [CHAR (1)]

T012
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
HBKID [CHAR (5)]

T015L
MANDT [CLNT (3)]
LZBKZ [CHAR (3)]

T042F
MANDT [CLNT (3)]
UZawe [CHAR (2)]

T042Z
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
ZLSCH [CHAR (1)]

T074U
MANDT [CLNT (3)]
KOART [CHAR (1)]
UMSKZ [CHAR (1)]

T880
MANDT [CLNT (3)]
RCOMP [CHAR (6)]

TBSL
MANDT [CLNT (3)]
BSCHL [CHAR (2)]

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]

FPRL_ITEM-EBELN = EKKO-EBELN

0..N

FPRL_ITEM-EBELP = EKPO-EBELP

0..N

FPRL_ITEM-APPLIC = FPRL_APPLIC-APPLICATION

0..N

FPRL_ITEM-LIST_ID = FPRL_HEADER-LIST_ID

0..N

FPRL_ITEM-STATUS = FPRL_ITEM_STAT-STATUS

0..N

FPRL_ITEM-ALEVEL = FPRL_LEVELS-ALEVEL

0..N

FPRL_ITEM-KUNNR = KNA1-KUNNR

0..N

FPRL_ITEM-LIFNR = LFA1-LIFNR

0..N

FPRL_ITEM-HKONT = SKB1-SAKNR

0..N

FPRL_ITEM-SAKNR = SKB1-SAKNR

0..N

FPRL_ITEM-BUKRS = T001-BUKRS

0..N

FPRL_ITEM-ZBUKR = T001-BUKRS

0..N

FPRL_ITEM-BLART = T003-BLART

0..N

FPRL_ITEM-LANDL = T005-LAND1

0..N

FPRL_ITEM-ZLSPR = T008-ZAHL1

0..N

FPRL_ITEM-HBKID = T012-HBKID

0..N

FPRL_ITEM-LZBKZ = T015L-LZBKZ

0..N

FPRL_ITEM-UZawe = T042F-UZawe

0..N

FPRL_ITEM-RZawe = T042Z-ZLSCH

0..N

FPRL_ITEM-UMSKZ = T074U-UMSKZ

0..N

FPRL_ITEM-VBUND = T880-RCOMP

0..N

FPRL_ITEM-BSCHL = TBSL-BSCHL

0..N

FPRL_ITEM-WAERS = TCURC-WAERS

0..N

FPRL_ITEM-GSBER = TGSB-GSBER

0..N