

SAP ABAP table GLE_MCA_STR_UI_POST_FIELDS {Posting line items of screen}

GLE_MCA_STR_UI_POST_FIELDS
BUKRS [CHAR (4)]
NEWBK [CHAR (4)]
BSCHL [CHAR (2)]
GSBER [CHAR (4)]
PARGB [CHAR (4)]
MWSKZ [CHAR (2)]
VBUND [CHAR (6)]
BEWAR [CHAR (3)]
KOSTL [CHAR (10)]
AUFNR [CHAR (12)]
VBEL2 [CHAR (10)]
POSN2 [NUMC (6)]
ETEN2 [NUMC (4)]
ANLN1 [CHAR (12)]
ANLN2 [CHAR (4)]
ANBWA [CHAR (3)]
SAKNR [CHAR (10)]
HKONT [CHAR (10)]
KUNNR [CHAR (10)]
LIFNR [CHAR (10)]
LZBKZ [CHAR (3)]
LANDL [CHAR (3)]
VNAME [CHAR (6)]
EGRUP [CHAR (3)]
PPRCT [CHAR (10)]
PSWSL [CUKY (5)]

GLE_MCA_STR_UI_POST_FIELDS-ANLN2 = ANLA-ANLN2

ANLA
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]
<u>ANLN1</u> [CHAR (12)]
<u>ANLN2</u> [CHAR (4)]

GLE_MCA_STR_UI_POST_FIELDS-ANLN1 = ANLH-ANLN1

ANLH
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]
<u>ANLN1</u> [CHAR (12)]

GLE_MCA_STR_UI_POST_FIELDS-AUFNR = AUFK-AUFNR

AUFK
<u>MANDT</u> [CLNT (3)]
AUFNR [CHAR (12)]

GLE_MCA_STR_UI_POST_FIELDS-KOSTL = CSKS-KOSTL

CSKS
<u>MANDT</u> [CLNT (3)]
<u>KOKRS</u> [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]

GLE_MCA_STR_UI_POST_FIELDS-KUNNR = KNA1-KUNNR

KNA1
<u>MANDT</u> [CLNT (3)]
KUNNR [CHAR (10)]

GLE_MCA_STR_UI_POST_FIELDS-LIFNR = LFA1-LIFNR

LFA1
<u>MANDT</u> [CLNT (3)]
<u>LIFNR</u> [CHAR (10)]

GLE_MCA_STR_UI_POST_FIELDS-BUKRS = T001-BUKRS

T001
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]

GLE_MCA_STR_UI_POST_FIELDS-NEWBK = T001-BUKRS

T007A
<u>MANDT</u> [CLNT (3)]
<u>KALSM</u> [CHAR (6)]
MWSKZ [CHAR (2)]

GLE_MCA_STR_UI_POST_FIELDS-MWSKZ = T007A-MWSKZ

T856
<u>MANDT</u> [CLNT (3)]
TRTYP [CHAR (3)]

GLE_MCA_STR_UI_POST_FIELDS-BEWAR = T856-TRTYP

GLE_MCA_STR_UI_POST_FIELDS-VBUND = T880-RCOMP

T880
<u>MANDT</u> [CLNT (3)]
<u>RCOMP</u> [CHAR (6)]

GLE_MCA_STR_UI_POST_FIELDS-ANBWA = TABW-BWASL

TABW
<u>MANDT</u> [CLNT (3)]
<u>BWASL</u> [CHAR (3)]

GLE_MCA_STR_UI_POST_FIELDS-BSCHL = TBSL-BSCHL

TBSL
<u>MANDT</u> [CLNT (3)]
<u>BSCHL</u> [CHAR (2)]

GLE_MCA_STR_UI_POST_FIELDS-PSWSL = TCURC-WAERS

TCURC
<u>MANDT</u> [CLNT (3)]
<u>WAERS</u> [CUKY (5)]

GLE_MCA_STR_UI_POST_FIELDS-GSBER = TGSB-GSBER

TGSB
<u>MANDT</u> [CLNT (3)]
GSBER [CHAR (4)]

GLE_MCA_STR_UI_POST_FIELDS-PARGB = TGSB-GSBER

GLE_MCA_STR_UI_POST_FIELDS-ETEN2 = VBEP-ETENR

VBEP
<u>MANDT</u> [CLNT (3)]
<u>VBELN</u> [CHAR (10)]
<u>POSNR</u> [NUMC (6)]
ETENR [NUMC (4)]

GLE_MCA_STR_UI_POST_FIELDS-VBEL2 = VBUK-VBELN

VBUK
<u>MANDT</u> [CLNT (3)]
<u>VBELN</u> [CHAR (10)]

GLE_MCA_STR_UI_POST_FIELDS-POSN2 = VBUP-POSNR

VBUP
<u>MANDT</u> [CLNT (3)]
<u>VBELN</u> [CHAR (10)]
<u>POSNR</u> [NUMC (6)]