

SAP ABAP table HCMT_BSP_PA_SP_R0022 {Single Screen for Infotype 0022 (Education)}

HCMT_BSP_PA_SP_R0022
SLART [CHAR (2)]
AUSBI [NUMC (8)]
AUSGR [NUMC (3)]
SLAND [CHAR (3)]
SLABS [CHAR (2)]
SLTP1 [NUMC (5)]
SLTP2 [NUMC (5)]
WAERS [CUKY (5)]

T005
<u>MANDT</u> [CLNT (3)]
<u>LAND1</u> [CHAR (3)]

T517T
<u>MANDT</u> [CLNT (3)]
<u>SPRSL</u> [LANG (1)]
<u>SLART</u> [CHAR (2)]

T517Y
<u>MANDT</u> [CLNT (3)]
<u>FACHR</u> [NUMC (5)]

T518A
<u>MANDT</u> [CLNT (3)]
<u>AUSBI</u> [NUMC (8)]

T518D
<u>MANDT</u> [CLNT (3)]
<u>AUSGR</u> [NUMC (3)]

T519T
<u>MANDT</u> [CLNT (3)]
<u>SPRSL</u> [LANG (1)]
<u>SLABS</u> [CHAR (2)]

TCURC
<u>MANDT</u> [CLNT (3)]
<u>WAERS</u> [CUKY (5)]

0..N

0..N

0..N

0..N

0..N

1

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

HCMT_BSP_PA_SP_R0022-SLAND = T005-LAND1

HCMT_BSP_PA_SP_R0022-SLART = T517T-SLART

HCMT_BSP_PA_SP_R0022-SLTP1 = T517Y-FACHR

HCMT_BSP_PA_SP_R0022-SLTP2 = T517Y-FACHR

HCMT_BSP_PA_SP_R0022-AUSBI = T518A-AUSBI

HCMT_BSP_PA_SP_R0022-AUSGR = T518D-AUSGR

HCMT_BSP_PA_SP_R0022-SLABS = T519T-SLABS

HCMT_BSP_PA_SP_R0022-WAERS = TCURC-WAERS