

SAP ABAP table HCMT_BSP_PA_XX_R0016 {Single Screen for Infotype 0016}

HCMT_BSP_PA_XX_R0016-KGZZH = T538C-ZEINH

T538C
<u>MANDT</u> [CLNT (3)]
<u>INFTY</u> [CHAR (4)]
<u>ZEINH</u> [CHAR (3)]

0..N HCMT_BSP_PA_XX_R0016-LFZZH = T538C-ZEINH 0..N

0..N HCMT_BSP_PA_XX_R0016-PRBEH = T538C-ZEINH 0..N

HCMT_BSP_PA_XX_R0016
CTTYP [CHAR (2)]
LFZZH [CHAR (3)]
KGZZH [CHAR (3)]
PRBEH [CHAR (3)]
KDGFR [CHAR (2)]
KDGF2 [CHAR (2)]
KONSL [CHAR (2)]

0..N HCMT_BSP_PA_XX_R0016-KONSL = T545T-KOSL1 0..N

0..N HCMT_BSP_PA_XX_R0016-KDGF2 = T547T-KDGFR 0..N

T545T
<u>MANDT</u> [CLNT (3)]
<u>KOSL1</u> [CHAR (2)]

0..N HCMT_BSP_PA_XX_R0016-KDGF2 = T547T-KDGFR 0..N

0..N HCMT_BSP_PA_XX_R0016-KDGF2 = T547T-KDGFR 0..N

T547T
<u>MANDT</u> [CLNT (3)]
<u>SPRSL</u> [LANG (1)]
<u>KDGFR</u> [CHAR (2)]

0..N HCMT_BSP_PA_XX_R0016-KDGF2 = T547T-KDGFR 0..N

0..N HCMT_BSP_PA_XX_R0016-KDGF2 = T547T-KDGFR 0..N

0..N HCMT_BSP_PA_XX_R0016-CTTYP = T547V-CTTYP 0..N

0..N HCMT_BSP_PA_XX_R0016-CTTYP = T547V-CTTYP 0..N

T547V
<u>MANDT</u> [CLNT (3)]
<u>CTTYP</u> [CHAR (2)]