

SAP ABAP table HCMT_BSP_PA_XX_R0278 {HR-CH: PF: Basic Data}

HCMT_BSP_PA_XX_R0278-EMA01 = T5CA0-ATTRI

HCMT_BSP_PA_XX_R0278-EMA02 = T5CA0-ATTRI

HCMT_BSP_PA_XX_R0278-EMA03 = T5CA0-ATTRI

HCMT_BSP_PA_XX_R0278-EMA04 = T5CA0-ATTRI

HCMT_BSP_PA_XX_R0278-EMA05 = T5CA0-ATTRI

HCMT_BSP_PA_XX_R0278-EMA06 = T5CA0-ATTRI

HCMT_BSP_PA_XX_R0278-EMA07 = T5CA0-ATTRI

HCMT_BSP_PA_XX_R0278-EMA08 = T5CA0-ATTRI

HCMT_BSP_PA_XX_R0278-ACL01 = T5CAP-ACLAS

HCMT_BSP_PA_XX_R0278-ACL02 = T5CAP-ACLAS

HCMT_BSP_PA_XX_R0278-ACL03 = T5CAP-ACLAS

HCMT_BSP_PA_XX_R0278-ACL04 = T5CAP-ACLAS

HCMT_BSP_PA_XX_R0278-ACL05 = T5CAP-ACLAS

HCMT_BSP_PA_XX_R0278-ACL06 = T5CAP-ACLAS

HCMT_BSP_PA_XX_R0278-ACL07 = T5CAP-ACLAS

HCMT_BSP_PA_XX_R0278-ACL08 = T5CAP-ACLAS

HCMT_BSP_PA_XX_R0278-KASSE = T5CP0-KASSE

HCMT_BSP_PA_XX_R0278
KASSE [CHAR (4)]
ACL01 [CHAR (2)]
EMA01 [NUMC (2)]
ACL02 [CHAR (2)]
EMA02 [NUMC (2)]
ACL03 [CHAR (2)]
EMA03 [NUMC (2)]
ACL04 [CHAR (2)]
EMA04 [NUMC (2)]
ACL05 [CHAR (2)]
EMA05 [NUMC (2)]
ACL06 [CHAR (2)]
EMA06 [NUMC (2)]
ACL07 [CHAR (2)]
EMA07 [NUMC (2)]
ACL08 [CHAR (2)]
EMA08 [NUMC (2)]

T5CA0
MANDT [CLNT (3)]
MOLGA [CHAR (2)]
APPLI [CHAR (2)]
ACLAS [CHAR (2)]
ATTRI [NUMC (2)]
ENDDA [DATS (8)]

T5CAP
MANDT [CLNT (3)]
MOLGA [CHAR (2)]
APPLI [CHAR (2)]
ACLAS [CHAR (2)]

T5CP0
MANDT [CLNT (3)]
KASSE [CHAR (4)]