SAP ABAP table ICLPART_DRV1 {First Party Driver (for Use in CMC)}

ADR2

CLIENT [CLNT (3)]
ADDRNUMBER [CHAR (10)]
PERSNUMBER [CHAR (10)]
DATE_FROM [DATS (8)]
CONSNUMBER [NUMC (3)]

ICLPART_DRV1-PHONEID = ADR2-CONSNUMBER 0..N

BUT000

CLIENT [CLNT (3)]
PARTNER [CHAR (10)]

ICLPART_DRV1-PARTICIPANT = BUT000-PARTNER 0..N

BUT020

CLIENT [CLNT (3)]
PARTNER [CHAR (10)]
ADDRNUMBER [CHAR (10)]

ICLPART_DRV1-MAILADDR = BUT020-ADDRNUMBER 0..N

ICLPART_DRV1-PHONEADDR = BUT020-ADDRNUMBER 0..N

ICLCLAIM

CLIENT [CLNT (3)]
ACTIVE [CHAR (1)]
CLAIM [CHAR (17)]

ICLPART_DRV1-CLAIM = ICLCLAIM-CLAIM 0..N

ICLPART_DRV1

CLIENT [CLNT (3)]
CLAIM [CHAR (17)]
PARTICIPANT [CHAR (10)]
CHANGEDBY [CHAR (12)]
MAILADDR [CHAR (10)]
PHONEADDR [CHAR (10)]
PHONEID [NUMC (3)]
RELTYPE [CHAR (1)]
PARTTYPE [CHAR (2)]
WIREPTYPE [CHAR (3)]
JUDGEMENT [CHAR (2)]

0..N 0..N 0..N

0..N

T000

MANDT [CLNT (3)]

0..N ICLPART_DRV1-CLIENT = T000-MANDT
0..N ICLPART_DRV1-JUDGEMENT = TICL010-JUDGEMENT 0..N
{0,1}

TICL010

CLIENT [CLNT (3)]
JUDGEMENT [CHAR (2)]

{0,1} ICLPART_DRV1-RELTYPE = TICL014-RELTYPE 0..N

TICL014

CLIENT [CLNT (3)]
RELTYPE [CHAR (1)]

ICLPART_DRV1-WIREPTYPE = TICL065-WIREPTYPE 0..N

TICL065

CLIENT [CLNT (3)]
WIREPTYPE [CHAR (3)]

0..N 0..N {0,1}

ICLPART_DRV1-PARTTYPE = TICL092-PARTTYPE 0..N

TICL092

CLIENT [CLNT (3)]
PARTTYPE [CHAR (2)]

ICLPART_DRV1-CHANGEDBY = USR02-BNAME 0..N

USR02

MANDT [CLNT (3)]
BNAME [CHAR (12)]