

SAP ABAP table IEQT_WL_ITEMS {Interim Statuses - Items}

IEQT_WL_ITEMS	
MANDT	[CLNT (3)]
EQUNR	[CHAR (18)]
LSTTYP	[CHAR (1)]
EVENT_DATE	[DATS (8)]
EVENT_TIME	[TIMS (6)]
QMNUM_REMOVAL	[CHAR (12)]
QMNUM_INSTALL	[CHAR (12)]
TPLNR	[CHAR (30)]
ABCKZ	[CHAR (1)]
SWERK	[CHAR (4)]
STORT	[CHAR (10)]
BEBER	[CHAR (3)]
PPSID	[NUMC (8)]
GSBER	[CHAR (4)]
KOKRS	[CHAR (4)]
KOSTL	[CHAR (10)]
PROID	[NUMC (8)]
BUKRS	[CHAR (4)]
ANLNR	[CHAR (12)]
ANLUN	[CHAR (4)]
DAUFN	[CHAR (12)]
AUFNR	[CHAR (12)]
VKORG	[CHAR (4)]
VTWEG	[CHAR (2)]
SPART	[CHAR (2)]
ADRNR	[CHAR (10)]
VKBUR	[CHAR (4)]
VKGRP	[CHAR (3)]

ADRC
CLIENT [CLNT (3)]
ADDRNUMBER [CHAR (10)]
DATE_FROM [DATS (8)]
NATION [CHAR (1)]

ANLA
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
ANLN1 [CHAR (12)]
ANLN2 [CHAR (4)]

ANLH
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
ANLN1 [CHAR (12)]

AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

CRID
MANDT [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]

CSKS
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]

IFLOT
MANDT [CLNT (3)]
TPLNR [CHAR (30)]

PRPS
MANDT [CLNT (3)]
PSPNR [NUMC (8)]

QMEL
MANDT [CLNT (3)]
QMNUM [CHAR (12)]

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

T357
MANDT [CLNT (3)]
WERKS [CHAR (4)]
BEBER [CHAR (3)]

T370C
MANDT [CLNT (3)]
ABCKZ [CHAR (1)]

T499S
MANDT [CLNT (3)]
WERKS [CHAR (4)]
STAND [CHAR (10)]

TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]

TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]

TVBVK
MANDT [CLNT (3)]
VKBUR [CHAR (4)]
VKGRP [CHAR (3)]

TVKBZ
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]
VKBUR [CHAR (4)]

TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]

TVKOV
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]

TVTA
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]

1 1 1 1 1 1

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

IEQT_WL_ITEMS-ADRNR = ADRC-ADDRNUMBER

IEQT_WL_ITEMS-ANLUN = ANLA-ANLN2

IEQT_WL_ITEMS-ANLNR = ANLH-ANLN1

IEQT_WL_ITEMS-AUFNR = AUFK-AUFNR

IEQT_WL_ITEMS-DAUFN = AUFK-AUFNR

IEQT_WL_ITEMS-PPSID = CRID-OBJID

IEQT_WL_ITEMS-KOSTL = CSKS-KOSTL

IEQT_WL_ITEMS-TPLNR = IFLOT-TPLNR

IEQT_WL_ITEMS-PROID = PRPS-PSPNR

IEQT_WL_ITEMS-QMNUM_INSTALL = QMEL-QMNUM

IEQT_WL_ITEMS-QMNUM_REMOVAL = QMEL-QMNUM

IEQT_WL_ITEMS-BUKRS = T001-BUKRS

IEQT_WL_ITEMS-SWERK = T001W-WERKS

IEQT_WL_ITEMS-BEBER = T357-BEBER

IEQT_WL_ITEMS-ABCKZ = T370C-ABCKZ

IEQT_WL_ITEMS-STORT = T499S-STAND

IEQT_WL_ITEMS-GSBER = TGSB-GSBER

IEQT_WL_ITEMS-KOKRS = TKA01-KOKRS

IEQT_WL_ITEMS-VKGRP = TVBVK-VKGRP

IEQT_WL_ITEMS-VKBUR = TVKBZ-VKBUR

IEQT_WL_ITEMS-VKORG = TVKO-VKORG

IEQT_WL_ITEMS-VTWEG = TVKOV-VTWEG

IEQT_WL_ITEMS-SPART = TVTA-SPART