

SAP ABAP table IF050 {Balance sheet/P&L (FI/FILC)}

IF050
<u>MANDT</u> [CLNT (3)]
<u>VERSIO</u> [CHAR (3)]
<u>PLACTI</u> [CHAR (1)]
<u>YEARB</u> [NUMC (4)]
<u>PERDE</u> [NUMC (3)]
<u>VERSO</u> [NUMC (2)]
<u>CLSCAT</u> [CHAR (1)]
<u>SUBGRP</u> [CHAR (3)]
<u>COMPNY</u> [CHAR (6)]
<u>COMCOD</u> [CHAR (4)]
<u>BUSARE</u> [CHAR (4)]
<u>BSVERS</u> [CHAR (4)]
<u>SUITEM</u> [CHAR (10)]
<u>LCITEM</u> [CHAR (10)]
<u>GLACCT</u> [CHAR (10)]
<u>VALTY</u> [CHAR (1)]
<u>MVCTGP</u> [CHAR (3)]
<u>LCVERS</u> [CHAR (3)]
<u>COUNTR</u> [CHAR (3)]
<u>CHACCT</u> [CHAR (4)]
<u>FSTAKY</u> [CHAR (10)]
<u>RECNR</u> [NUMC (8)]
<u>COMCOD_WAERS</u> [CUKY (5)]
<u>COMPNY_CURR</u> [CUKY (5)]
<u>T852V_RCURR</u> [CUKY (5)]
<u>VERSO_WAERS</u> [CUKY (5)]
<u>QUANTY_UNI</u> [UNIT (3)]

SKA1
<u>MANDT</u> [CLNT (3)]
<u>KTOPL</u> [CHAR (4)]
<u>SAKNR</u> [CHAR (10)]

T000
<u>MANDT</u> [CLNT (3)]

T001
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]

T004
<u>MANDT</u> [CLNT (3)]
<u>KTOPL</u> [CHAR (4)]

T005
<u>MANDT</u> [CLNT (3)]
<u>LAND1</u> [CHAR (3)]

T006
<u>MANDT</u> [CLNT (3)]
<u>MSEHI</u> [UNIT (3)]

T011
<u>MANDT</u> [CLNT (3)]
<u>VERSN</u> [CHAR (4)]

T242V
<u>MANDT</u> [CLNT (3)]
<u>VERSO</u> [NUMC (2)]

T242W
<u>MANDT</u> [CLNT (3)]
<u>VALTY</u> [CHAR (1)]

T852
<u>MANDT</u> [CLNT (3)]
<u>RSUBD</u> [CHAR (3)]

T852N
<u>MANDT</u> [CLNT (3)]
<u>FSCAT</u> [CHAR (1)]

T854
<u>MANDT</u> [CLNT (3)]
<u>ITEM</u> [CHAR (10)]

T856X
<u>MANDT</u> [CLNT (3)]
<u>RWGRP</u> [CHAR (3)]

T858
<u>MANDT</u> [CLNT (3)]
<u>RVERS</u> [CHAR (3)]

T880
<u>MANDT</u> [CLNT (3)]
<u>RCOMP</u> [CHAR (6)]

TCURC
<u>MANDT</u> [CLNT (3)]
<u>WAERS</u> [CUKY (5)]

TGSB
<u>MANDT</u> [CLNT (3)]
<u>GSBER</u> [CHAR (4)]

TKCVS
<u>MANDT</u> [CLNT (3)]
<u>VERSIO</u> [CHAR (3)]

