

SAP ABAP table INM_TS_ITEM_CHG {Externally Modifiable Item Attributes}

INM_TS_ITEM_CHG-UNIT = /RPM/CAP_UNITS-UNIT

INM_TS_ITEM_CHG
INITIATIVE_TYPE [CHAR (15)]
CATEGORY [NUMC (4)]
SUBCATEGORY [NUMC (4)]
PTYPE [NUMC (4)]
TTYPE [NUMC (4)]
CURRENCY [CUKY (5)]
PERIODTYPE [NUMC (2)]
UNIT [UNIT (3)]
PRIORITY_GROUP [NUMC (2)]
CAP_PERIODTYPE [NUMC (2)]
RISK_GROUP [NUMC (2)]
RISK_GROUP_D [NUMC (2)]

_RPM_CAP_UNITS
CLIENT [CLNT (3)]
<u>UNIT</u> [UNIT (3)]

_RPM_CURRENCY
CLIENT [CLNT (3)]
<u>CURRENCY</u> [CUKY (5)]

_RPM_ITEM_TYPE
CLIENT [CLNT (3)]
<u>ITEM_TYPE</u> [CHAR (15)]

_RPM_PERIOD_TYPE
CLIENT [CLNT (3)]
<u>PERIODTYPE</u> [NUMC (2)]

RPM_PROJ_CAT
<u>MANDT</u> [CLNT (3)]
<u>CATEGORY</u> [NUMC (4)]

RPM_PROJ_PRGRP
<u>MANDT</u> [CLNT (3)]
<u>PRIORITY_GROUP</u> [NUMC (2)]

RPM_PROJ_RKGRP
<u>MANDT</u> [CLNT (3)]
<u>RISK_GROUP</u> [NUMC (2)]

RPM_PROJ_SUBCAT
<u>MANDT</u> [CLNT (3)]
<u>CATEGORY</u> [NUMC (4)]
<u>SUBCATEGORY</u> [NUMC (4)]

RPM_PROJ_TTYPE
<u>MANDT</u> [CLNT (3)]
<u>CATEGORY</u> [NUMC (4)]
<u>TTYPE</u> [NUMC (4)]

RPM_PROJ_TYPE
<u>MANDT</u> [CLNT (3)]
<u>CATEGORY</u> [NUMC (4)]
<u>PTYPE</u> [NUMC (4)]

0..N/0..N/

1

1

0..N

0..N

0..N

1

1

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

INM_TS_ITEM_CHG-CURRENCY = /RPM/CURRENCY-CURRENCY

INM_TS_ITEM_CHG-INITIATIVE_TYPE = /RPM/ITEM_TYPE-ITEM_TYPE

INM_TS_ITEM_CHG-CAP_PERIODTYPE = /RPM/PERIOD_TYPE-PERIODTYPE

INM_TS_ITEM_CHG-PERIODTYPE = /RPM/PERIOD_TYPE-PERIODTYPE

INM_TS_ITEM_CHG-CATEGORY = RPM_PROJ_CAT-CATEGORY

INM_TS_ITEM_CHG-PRIORITY_GROUP = RPM_PROJ_PRGRP-PRIORITY_GROUP

INM_TS_ITEM_CHG-RISK_GROUP = RPM_PROJ_RKGRP-RISK_GROUP

INM_TS_ITEM_CHG-RISK_GROUP_D = RPM_PROJ_RKGRP-RISK_GROUP

INM_TS_ITEM_CHG-SUBCATEGORY = RPM_PROJ_SUBCAT-SUBCATEGORY

INM_TS_ITEM_CHG-TTYPE = RPM_PROJ_TTYPE-TTYPE

INM_TS_ITEM_CHG-PTYPE = RPM_PROJ_TYPE-PTYPE