

SAP ABAP table IVIORA { Generated Table for View }

IVIORA-AENNR = AENR-AENNR

IVIORA
MANDT [CLNT (3)]
AUFNR [CHAR (12)]
IWERK [CHAR (4)]
ILOAN [CHAR (12)]
OBKNR [INT4 (10)]
AUART [CHAR (4)]
REFNR [CHAR (12)]
BUKRS [CHAR (4)]
WERKS [CHAR (4)]
GSBER [CHAR (4)]
KOKRS [CHAR (4)]
KOSTV [CHAR (10)]
STORT [CHAR (10)]
SOWRK [CHAR (4)]
WAERS [CUKY (5)]
KVEWE [CHAR (1)]
KAPPL [CHAR (2)]
KALSM [CHAR (6)]
ABKRS [NUMC (2)]
KSTAR [CHAR (10)]
KOSTL [CHAR (10)]
CYCLE [CHAR (10)]
OBJNR [CHAR (22)]
PRCTR [CHAR (10)]
PSPEL [NUMC (8)]
AWSLS [CHAR (6)]
ABGSL [CHAR (6)]
TXJCD [CHAR (15)]
FUNC_AREA [CHAR (16)]
KDAUF [CHAR (10)]
IVPRO [CHAR (6)]
LOGSYSTEM [CHAR (10)]
ABUKR [CHAR (4)]
SIZECL [CHAR (2)]
IZWEK [CHAR (2)]
UMWKZ [CHAR (5)]
ZSCHM [CHAR (7)]
ANFAUFNR [CHAR (12)]
BEMOT [CHAR (2)]
VERAA_USER [CHAR (12)]
VNAME [CHAR (6)]
RECID [CHAR (2)]
ETYPY [CHAR (3)]
JV_JIBCL [CHAR (3)]
JV_JIBSA [CHAR (5)]
FERC_IND [CHAR (4)]
GMEIN [UNIT (3)]
PLNBEZ [CHAR (18)]
PLNAW [CHAR (1)]
PVERW [CHAR (3)]
PLNME [UNIT (3)]
PAENR [CHAR (12)]
PLGRP [CHAR (3)]
STLBEZ [CHAR (18)]
STLST [NUMC (2)]
SBMEH [UNIT (3)]
SAENR [CHAR (12)]
STLAN [CHAR (1)]
DISPO [CHAR (3)]
FEVOR [CHAR (3)]
FHORI [CHAR (3)]
TERKZ [CHAR (1)]
NTZUE [CHAR (12)]
PROFID [CHAR (7)]
PRONR [NUMC (8)]
RSHID [NUMC (8)]
RSNID [NUMC (8)]
CSPLIT [CHAR (4)]
AENNR [CHAR (12)]
CHSCH [CHAR (6)]
LEAD_AUFNR [CHAR (12)]
SFCPF [CHAR (6)]
REVNR [CHAR (8)]

IVIORA-MANDT = T000-MANDT

IVIORA-ABUKR = T001-BUKRS

IVIORA-BUKRS = T001-BUKRS

IVIORA-SOWRK = T001W-WERKS

IVIORA-WERKS = T001W-WERKS

IVIORA-AUART = T003O-AUART

IVIORA-GMEIN = T006-MSEHI

IVIORA-PLNME = T006-MSEHI

IVIORA-SBMEH = T006-MSEHI

IVIORA-PLGRP = T024A-FEVOR

IVIORA-DISPO = T024D-DISPO

IVIORA-FEVOR = T024F-FEVOR

IVIORA-IZWEK = T087I-IZWEK

IVIORA-UMWKZ = T087K-UMWKZ

IVIORA-REVNR = T352R-REVNR

IVIORA-IWERK = T399I-IWERK

IVIORA-PVERW = T411-VERWE

IVIORA-STLST = T415S-STLST

IVIORA-STLAN = T416-STLAN

IVIORA-FHORI = T436A-FHORI

IVIORA-TERKZ = T482-TERMKZ

IVIORA-STORT = T499S-STAND

IVIORA-KAPPL = T681A-KAPPL

IVIORA-KVEWE = T681V-KVEWE

IVIORA-CHSCH = T683-KALSM

IVIORA-KALSM = T683-KALSM

IVIORA-JV_JIBCL = T8J6A-CLASS

IVIORA-JV_JIBSA = T8J6C-SUBCLASS

IVIORA-ETYPY = T8JG-ETYPY

IVIORA-RECID = T8JJ-RECID

IVIORA-VNAME = T8JV-VNAME

IVIORA-SIZECL = TAIF5-SIZECL

IVIORA-IVPRO = TAPRF-IVPRO

IVIORA-LOGSYSTEM = TBDLS-LOGSYS

IVIORA-BEMOT = TBMOT-BEMOT

IVIORA-PLNAW = TCA09-PLNAW

IVIORA-PROFID = TCN41-PROFIDNETZ

IVIORA-SFCPF = TCO43-CO_PRODPRF

IVIORA-WAERS = TCURC-WAERS

IVIORA-FUNC_AREA = TFKB-FKBER

IVIORA-GSBER = TGSB-GSBER

IVIORA-KOKRS = TKA01-KOKRS

IVIORA-ABGSL = TKKAA-ABGSL

IVIORA-ABKRS = TKO08-ABKRS

IVIORA-AWSLS = TKV01-AWSLS

IVIORA-ZSCHM = TPI01-ZSCHM

IVIORA-TXJCD = TTXJ-TXJCD

IVIORA-VERAA_USER = USR02-BNAME

IVIORA-KDAUF = VBUK-VBELN

AENR
MANDT [CLNT (3)]
AENNR [CHAR (12)]

AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

CEPC
MANDT [CLNT (3)]
PRCTR [CHAR (10)]
DATBI [DATS (8)]
KOKRS [CHAR (4)]

CRID
MANDT [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]

CSKB
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KSTAR [CHAR (10)]
DATBI [DATS (8)]

CSKS
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]

FERC_C7
MANDT [CLNT (3)]
IND [CHAR (4)]

ILOA
MANDT [CLNT (3)]
ILOAN [CHAR (12)]

MAKV
MANDT [CLNT (3)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
CSPLIT [CHAR (4)]

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]

PROJ
MANDT [CLNT (3)]
PSPNR [NUMC (8)]

PRPS
MANDT [CLNT (3)]
PSPNR [NUMC (8)]

SER00
MANDT [CLNT (3)]
OBKNR [INT4 (10)]

T000
MANDT [CLNT (3)]

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

T003O
CLIENT [CLNT (3)]
AUART [CHAR (4)]

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

T024A
MANDT [CLNT (3)]
WERKS [CHAR (4)]
FEVOR [CHAR (3)]

T024D
MANDT [CLNT (3)]
WERKS [CHAR (4)]
DISPO [CHAR (3)]

T024F
MANDT [CLNT (3)]
WERKS [CHAR (4)]
FEVOR [CHAR (3)]

T087I
MANDT [CLNT (3)]
IZWEK [CHAR (2)]

T087K
MANDT [CLNT (3)]
UMWKZ [CHAR (5)]

T352R
MANDT [CLNT (3)]
IWERK [CHAR (4)]
REVNR [CHAR (8)]

T399I
MANDT [CLNT (3)]
IWERK [CHAR (4)]

T411
MANDT [CLNT (3)]
VERWE [CHAR (3)]

T415S
MANDT [CLNT (3)]
STLST [NUMC (2)]

T416
MANDT [CLNT (3)]
STLAN [CHAR (1)]

T436A
MANDT [CLNT (3)]
WERKS [CHAR (4)]
FHORI [CHAR (3)]

T482
MANDT [CLNT (3)]
TERMKZ [CHAR (1)]

T499S
MANDT [CLNT (3)]
WERKS [CHAR (4)]
STAND [CHAR (10)]

T681A
KAPPL [CHAR (2)]

T681V
KVEWE [CHAR (1)]

T683
MANDT [CLNT (3)]
KVEWE [CHAR (1)]
KAPPL [CHAR (2)]
KALSM [CHAR (6)]

T8J6A
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
CLASS [CHAR (3)]

T8J6C
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
CLASS [CHAR (3)]
SUBCLASS [CHAR (5)]

T8JG
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
VNAME [CHAR (6)]
ETYPY [CHAR (3)]
EDATE [NUMC (8)]

T8JJ
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
RECID [CHAR (2)]

T8JV
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
VNAME [CHAR (6)]

TAIF5
MANDT [CLNT (3)]
SIZECL [CHAR (2)]

TAPRF
MANDT [CLNT (3)]
IVPRO [CHAR (6)]

TBDLS
LOGSYS [CHAR (10)]

TBMOT
MANDT [CLNT (3)]
BEMOT [CHAR (2)]

TCA09
MANDT [CLNT (3)]
PLNAW [CHAR (1)]

TCN41
MANDT [CLNT (3)]
PLNAW [CHAR (1)]
PROFIDNETZ [CHAR (7)]

TCO43
MANDT [CLNT (3)]
WERKS [CHAR (4)]
CO_PRODPRF [CHAR (6)]

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

TFKB
MANDT [CLNT (3)]
FKBER [CHAR (16)]

TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]

TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]

TKKAA
MANDT [CLNT (3)]
ABGSL [CHAR (6)]

TKO08
CLIENT [CLNT (3)]
KOKRS [CHAR (4)]
ABKRS [NUMC (2)]

TKV01
MANDT [CLNT (3)]
AWOBA [CHAR (2)]
AWSLS [CHAR (6)]

TPI01
MANDT [CLNT (3)]
ZSCHM [CHAR (7)]

TTXJ
MANDT [CLNT (3)]
KALSM [CHAR (6)]
TXJCD [CHAR (15)]

USR02
MANDT [CLNT (3)]
BNAME [CHAR (12)]

VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]