

SAP ABAP table J_1BAAV {Generated Table for View}

J_1BAAV-NFTYPC = J_1BAA-NFTYPE

J_1BAA
<u>MANDT</u> [CLNT (3)]
<u>NFTYPE</u> [CHAR (2)]

J_1BAAV-NFTYPECONTI = J_1BAA-NFTYPE

J_1BAD
<u>MANDT</u> [CLNT (3)]
<u>PARVW</u> [CHAR (2)]

J_1BAAV-PARVW = J_1BAD-PARVW

J_1BAQ
<u>MANDT</u> [CLNT (3)]
<u>FORM</u> [CHAR (4)]

J_1BAAV-FORM = J_1BAQ-FORM

J_1BAAV-FORM_SCAN = J_1BAQ-FORM

J_1BDOCTYPES
<u>MANDT</u> [CLNT (3)]
<u>DOCTYP</u> [CHAR (1)]

J_1BAAV-DOCTYP = J_1BDOCTYPES-DOCTYP

J_1BAAV-ITMTYP = J_1BITEMTYPES-ITMTYP

J_1BITEMTYPES
<u>MANDT</u> [CLNT (3)]
<u>ITMTYP</u> [CHAR (2)]

J_1BAAV-TEXTKEY = J_1BMMNFTT-TEXTKEY

J_1BMMNFTT
<u>MANDT</u> [CLNT (3)]
<u>TEXTKEY</u> [CHAR (4)]

J_1BAAV-MANDT = T000-MANDT

T000
<u>MANDT</u> [CLNT (3)]

J_1BAAV-GEWEI = T006-MSEHI

T006
<u>MANDT</u> [CLNT (3)]
<u>MSEHI</u> [UNIT (3)]

J_1BAAV
<u>MANDT</u> [CLNT (3)]
<u>NFTYPE</u> [CHAR (2)]
<u>DOCTYP</u> [CHAR (1)]
<u>NFTYPC</u> [CHAR (2)]
<u>FORM</u> [CHAR (4)]
<u>PARVW</u> [CHAR (2)]
<u>ITMTYP</u> [CHAR (2)]
<u>TEXTKEY</u> [CHAR (4)]
<u>GEWEI</u> [UNIT (3)]
<u>NFTYPECONTI</u> [CHAR (2)]
<u>FORM_SCAN</u> [CHAR (4)]

{0,1}

1

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

1

1

1

1

1

1

1