

SAP ABAP table J_7LC69_V {Generated Table for View}

J_7LC69_V-VPARTG = J_7LC17-VPART

0..N

J_7LC17
<u>MANDT</u> [CLNT (3)]
<u>VPART</u> [NUMC (2)]

J_7LC69_V-VPARTS = J_7LC17-VPART

0..N

J_7LC20

<u>MANDT</u> [CLNT (3)]
<u>VPEBENE</u> [NUMC (2)]

J_7LC69_V-VEBENE = J_7LC20-VPEBENE

0..N

0..N, 0..N

J_7LC68

<u>MANDT</u> [CLNT (3)]
<u>ENTNA</u> [CHAR (6)]
<u>BUKRS</u> [CHAR (4)]
<u>LAND1</u> [CHAR (3)]
<u>DATAB</u> [DATS (8)]
<u>DATBI</u> [DATS (8)]

J_7LC69_V-BUKRS = J_7LC68-BUKRS

0..N

J_7LC69_V-DATAB = J_7LC68-DATAB

0..N

J_7LC69_V-ENTNA = J_7LC68-ENTNA

0..N

J_7LC69_V-LAND1 = J_7LC68-LAND1

0..N

J_7LE06

<u>MANDT</u> [CLNT (3)]
<u>ENTNR</u> [CHAR (10)]
<u>LAND1</u> [CHAR (3)]
<u>INFOK</u> [CHAR (5)]

J_7LC69_V-INFOK = J_7LE06-INFOK

0..N

J_7LC69_V-FUELLG = J_7LE07-FUELLG

0..N

J_7LE07

<u>MANDT</u> [CLNT (3)]
<u>ENTNR</u> [CHAR (10)]
<u>LAND1</u> [CHAR (3)]
<u>FUELLG</u> [CHAR (5)]

J_7LC69_V-HDLST = J_7LE13-HDLST

0..N

J_7LE13

<u>MANDT</u> [CLNT (3)]
<u>ENTNR</u> [CHAR (10)]
<u>LAND1</u> [CHAR (3)]
<u>HDLST</u> [NUMC (5)]

J_7LC69_V-VRPKT = J_7LE16-VRPKT

0..N

J_7LE16

<u>MANDT</u> [CLNT (3)]
<u>ENTNR</u> [CHAR (10)]
<u>LAND1</u> [CHAR (3)]
<u>VRPKT</u> [CHAR (5)]

J_7LC69_V-STOFF = J_7LS01-STOFI

0..N

J_7LS01

<u>MANDT</u> [CLNT (3)]
<u>STOFI</u> [CHAR (6)]

J_7LC69_V-ENTNR = LFA1-LIFNR

0..N

LFA1

<u>MANDT</u> [CLNT (3)]
<u>LIFNR</u> [CHAR (10)]

J_7LC69_V-MANDT = T000-MANDT

0..N

T000

<u>MANDT</u> [CLNT (3)]

0..N

J_7LC69_V
<u>MANDT</u> [CLNT (3)]
<u>ENTNA</u> [CHAR (6)]
<u>BUKRS</u> [CHAR (4)]
<u>LAND1</u> [CHAR (3)]
<u>DATAB</u> [DATS (8)]
<u>DATBI</u> [DATS (8)]
<u>LFDNR</u> [NUMC (3)]
<u>ENTNR</u> [CHAR (10)]
<u>HDLST</u> [NUMC (5)]
<u>FUELLG</u> [CHAR (5)]
<u>INFOK</u> [CHAR (5)]
<u>VPARTG</u> [NUMC (2)]
<u>VPARTS</u> [NUMC (2)]
<u>VEBENE</u> [NUMC (2)]
<u>VRPKT</u> [CHAR (5)]
<u>STOFF</u> [CHAR (6)]

00M:N, 0..N