

SAP ABAP table J_7LIZFV_V_VPKCW {Generated Table for View}

J_7LIZFV_V_VPKCW-VPARTG = J_7LC17-VPART

0..N

J_7LC17
<u>MANDT</u> [CLNT (3)]
<u>VPART</u> [NUMC (2)]

J_7LIZFV_V_VPKCW-VPARTS = J_7LC17-VPART

0..N

J_7LC20
<u>MANDT</u> [CLNT (3)]
<u>VPEBENE</u> [NUMC (2)]

J_7LIZFV_V_VPKCW-VPEBENE = J_7LC20-VPEBENE

0..N

J_7LIZFV_V_VPKCW-ENTNA = J_7LE00-ENTNA

{0,1}

J_7LE00
<u>MANDT</u> [CLNT (3)]
<u>ENTNA</u> [CHAR (6)]

J_7LIZFV_V_VPKCW-ENTNR = J_7LE01-ENTNR

0..N

J_7LE01
<u>MANDT</u> [CLNT (3)]
<u>ENTNR</u> [CHAR (10)]
<u>LAND1</u> [CHAR (3)]

J_7LIZFV_V_VPKCW-LAND1 = J_7LE01-LAND1

0..N

J_7LIZFV_V_VPKCW-VRPKT = J_7LE16-VRPKT

0..N

J_7LE16
<u>MANDT</u> [CLNT (3)]
<u>ENTNR</u> [CHAR (10)]
<u>LAND1</u> [CHAR (3)]
<u>VRPKT</u> [CHAR (5)]

J_7LIZFV_V_VPKCW-MUSTERVPRNR = J_7LV01-VRPNR

1

J_7LV01
<u>MANDT</u> [CLNT (3)]
<u>VRPNR</u> [CHAR (18)]
<u>VARIANTE</u> [CHAR (18)]

J_7LIZFV_V_VPKCW-VRPNR = J_7LV01-VRPNR

0..N

J_7LIZFV_V_VPKCW-VVARIANTE = J_7LV01-VARIANTE

0..N

J_7LIZFV_V_VPKCW-GSTFN = MGEF-STOFF

0..N

MGEF
<u>MANDT</u> [CLNT (3)]
<u>STOFF</u> [CHAR (18)]
<u>REGKZ</u> [CHAR (3)]

J_7LIZFV_V_VPKCW-MANDT = T000-MANDT

0..N

T000
<u>MANDT</u> [CLNT (3)]

J_7LIZFV_V_VPKCW-SPRASV = T002-SPRAS

0..N

T002
<u>SPRAS</u> [LANG (1)]

J_7LIZFV_V_VPKCW-GEWEI = T006-MSEHI

0..N

T006
<u>MANDT</u> [CLNT (3)]
<u>MSEHI</u> [UNIT (3)]

J_7LIZFV_V_VPKCW-STOKL = T023-MATKL

0..N

T023
<u>MANDT</u> [CLNT (3)]
<u>MATKL</u> [CHAR (9)]

J_7LIZFV_V_VPKCW
<u>MANDT</u> [CLNT (3)]
<u>STOFI</u> [CHAR (6)]
<u>SPRASV</u> [LANG (1)]
<u>DATBI</u> [DATS (8)]
<u>VRPNR</u> [CHAR (18)]
<u>VVARIANTE</u> [CHAR (18)]
<u>ENTNR</u> [CHAR (10)]
<u>LAND1</u> [CHAR (3)]
<u>STOKL</u> [CHAR (9)]
<u>GSTFN</u> [CHAR (18)]
<u>GEWEI</u> [UNIT (3)]
<u>VPARTG</u> [NUMC (2)]
<u>VPARTS</u> [NUMC (2)]
<u>VRPKT</u> [CHAR (5)]
<u>VPEBENE</u> [NUMC (2)]
<u>ENTNA</u> [CHAR (6)]
<u>MUSTERVPRNR</u> [CHAR (18)]

0..N

0..N

01N