

SAP ABAP table JKVWWWTEMP {Generated Table for View}

JKVWWWTEMP-BEZUGSTYP = JDTBEZTYP-BEZTYP

JDTBEZTYP
<u>MANDT</u> [CLNT (3)]
<u>DRERTR</u> [CHAR (8)]
<u>PVATRA</u> [CHAR (8)]
BEZTYP [CHAR (2)]

JKVWWWTEMP-DRERZ = JDTDREER-DRERZ

JDTDREER
<u>MANDT</u> [CLNT (3)]
DRERZ [CHAR (8)]

JKVWWWTEMP-PVA = JDTPVA-PVA

JDTPVA
<u>MANDT</u> [CLNT (3)]
<u>DRERZ</u> [CHAR (8)]
PVA [CHAR (8)]

JKVWWWTEMP-MATNR = JMTMAT-MATNR

JMTMAT
<u>MANDT</u> [CLNT (3)]
MATNR [CHAR (18)]

JKVWWWTEMP-SPRAS = T002-SPRAS

T002
SPRAS [LANG (1)]

JKVWWWTEMP-BANKS = T005-LAND1

T005
<u>MANDT</u> [CLNT (3)]
<u>LAND1</u> [CHAR (3)]

JKVWWWTEMP-LAND1 = T005-LAND1

T005S
<u>MANDT</u> [CLNT (3)]
<u>LAND1</u> [CHAR (3)]
BLAND [CHAR (3)]

JKVWWWTEMP-LAND1_INIT = T005-LAND1

JKVWWWTEMP-REGIO = T005S-BLAND

T042Z
<u>MANDT</u> [CLNT (3)]
<u>LAND1</u> [CHAR (3)]
ZLSCH [CHAR (1)]

JKVWWWTEMP-ZLSCH = T042Z-ZLSCH

JKVWWWTEMP-KDGRP = T151-KDGRP

T151
<u>MANDT</u> [CLNT (3)]
KDGRP [CHAR (2)]

JKVWWWTEMP-KONDA = T188-KONDA

T188
<u>MANDT</u> [CLNT (3)]
KONDA [CHAR (2)]

JKVWWWTEMP-TITEL = T535N-TITEL

T535N
<u>MANDT</u> [CLNT (3)]
ART [CHAR (1)]
TITEL [CHAR (15)]

JKVWWWTEMP-ISM_RCCVV = TCCRC-RCODE

TCCRC
<u>MANDT</u> [CLNT (3)]
RCATG [CHAR (1)]
RCODE [CHAR (4)]

JKVWWWTEMP-WAERS = TCURC-WAERS

TCURC
<u>MANDT</u> [CLNT (3)]
WAERS [CUKY (5)]

JKVWWWTEMP-KURST = TCURV-KURST

TCURV
<u>MANDT</u> [CLNT (3)]
KURST [CHAR (4)]

JKVWWWTEMP-PERFK = TFACD-IDENT

TFACD
IDENT [CHAR (2)]

JKVWWWTEMP-AUART = TJAK-AUART

TJAK
<u>MANDT</u> [CLNT (3)]
AUART [CHAR (4)]

JKVWWWTEMP-POART = TJAP-POART

TJAP
<u>MANDT</u> [CLNT (3)]
POART [CHAR (2)]

JKVWWWTEMP-BEZPER = TJD09-BEZPER

TJD09
<u>MANDT</u> [CLNT (3)]
BEZPER [CHAR (5)]

JKVWWWTEMP-ANRED = TJG43-JANRED

TJG43
<u>MANDT</u> [CLNT (3)]
JANRED [CHAR (2)]

JKVWWWTEMP-FKPER = TJK01-FKPER

TJK01
<u>MANDT</u> [CLNT (3)]
FKPER [CHAR (2)]

JKVWWWTEMP-KUENDGRD = TJK83-KUENDGRD

TJK83
<u>MANDT</u> [CLNT (3)]
KUENDGRD [CHAR (3)]

JKVWWWTEMP-BEZUGGRD = TJK87-BEZUGGRD

TJK87
<u>MANDT</u> [CLNT (3)]
BEZUGGRD [CHAR (3)]

JKVWWWTEMP-RCODE = TJKRRC-RCODE

TJKRRC
<u>MANDT</u> [CLNT (3)]
RCODE [CHAR (4)]

JKVWWWTEMP-KEY_CHECK_AG = TJKWWW_CHECK-KEY_CHECK

TJKWWW_CHECK
<u>MANDT</u> [CLNT (3)]
KEY_CHECK [CHAR (10)]

JKVWWWTEMP-KEY_CHECK_RE = TJKWWW_CHECK-KEY_CHECK

JKVWWWTEMP-KEY_CHECK_VM = TJKWWW_CHECK-KEY_CHECK

JKVWWWTEMP-KEY_CHECK_WE = TJKWWW_CHECK-KEY_CHECK

TJKWWW_FIX
<u>MANDT</u> [CLNT (3)]
KEY_FIX [CHAR (10)]

JKVWWWTEMP-KEY_FIX = TJKWWW_FIX-KEY_FIX

TJKWWW_VAR
<u>MANDT</u> [CLNT (3)]
KEY_VAR [CHAR (10)]

JKVWWWTEMP-KEY_VAR = TJKWWW_VAR-KEY_VAR

JKVWWWTEMP-POSTDIRECTIONAL = TJS41-DIRECTIONAL

TJS41
<u>LAND1</u> [CHAR (3)]
DIRECTIONAL [CHAR (10)]

JKVWWWTEMP-PREDIRECTIONAL = TJS41-DIRECTIONAL

JKVWWWTEMP-LIEFERART = TJV01-LIEFERART

TJV01
<u>MANDT</u> [CLNT (3)]
LIEFERART [CHAR (2)]

JKVWWWTEMP-WERBTAEAG = TJW09-WERBTAEAG

TJW09
<u>MANDT</u> [CLNT (3)]
WERBTAEAG [CHAR (10)]

JKVWWWTEMP-WERBEAKT = TJWAK-WERBEAKT

TJWAK
<u>MANDT</u> [CLNT (3)]
WERBEAKT [CHAR (8)]

JKVWWWTEMP-WERBEART = TJWAR-WERBEART

TJWAR
<u>MANDT</u> [CLNT (3)]
WERBEART [CHAR (4)]

JKVWWWTEMP-SPART = TSPA-SPART

TSPA
<u>MANDT</u> [CLNT (3)]
SPART [CHAR (2)]

JKVWWWTEMP-VKBUR = TVBUR-VKBUR

TVBUR
<u>MANDT</u> [CLNT (3)]
VKBUR [CHAR (4)]

JKVWWWTEMP-CCINS = TVCIN-CCINS

TVCIN
<u>MANDT</u> [CLNT (3)]
CCINS [CHAR (4)]

JKVWWWTEMP-CCTYP = TVCTY-CCTYP

TVCTY
<u>MANDT</u> [CLNT (3)]
CCTYP [CHAR (2)]

JKVWWWTEMP-VKGRP = TVKGR-VKGRP

TVKGR
<u>MANDT</u> [CLNT (3)]
VKGRP [CHAR (3)]

JKVWWWTEMP-VKORG = TVKO-VKORG

TVKO
<u>MANDT</u> [CLNT (3)]
VKORG [CHAR (4)]

JKVWWWTEMP-VTWEG = TVTW-VTWEG

TVTW
<u>MANDT</u> [CLNT (3)]
VTWEG [CHAR (2)]

JKVWWWTEMP
<u>MANDT</u> [CLNT (3)]
<u>SESSIONNO</u> [CHAR (10)]
<u>VKORG</u> [CHAR (4)]
<u>VTWEG</u> [CHAR (2)]
<u>SPART</u> [CHAR (2)]
<u>AUART</u> [CHAR (4)]
<u>VKBUR</u> [CHAR (4)]
<u>VKGRP</u> [CHAR (3)]
<u>KURST</u> [CHAR (4)]
<u>WAERS</u> [CUKY (5)]
<u>XWEOBL</u> [CHAR (1)]
<u>XREOBL</u> [CHAR (1)]
<u>KEY_CHECK_AG</u> [CHAR (10)]
<u>KEY_CHECK_WE</u> [CHAR (10)]
<u>KEY_CHECK_RE</u> [CHAR (10)]
<u>KEY_CHECK_VM</u> [CHAR (10)]
<u>DATA_TARGET</u> [CHAR (1)]
<u>DRERZ</u> [CHAR (8)]
<u>PVA</u> [CHAR (8)]
<u>BEZUGSTYP</u> [CHAR (2)]
<u>LIEFERART</u> [CHAR (2)]
<u>POART</u> [CHAR (2)]
<u>WERBEART</u> [CHAR (4)]
<u>WERBEAKT</u> [CHAR (8)]
<u>BEZPER</u> [CHAR (5)]
<u>BEZUGGRD</u> [CHAR (3)]
<u>PERFK</u> [CHAR (2)]
<u>FKPER</u> [CHAR (2)]
<u>KDGRP</u> [CHAR (2)]
<u>KONDA</u> [CHAR (2)]
<u>RCODE</u> [CHAR (4)]
<u>ETMENGE</u> [NUMC (10)]
<u>MATNR</u> [CHAR (18)]
<u>VALDAYS</u> [NUMC (3)]
<u>VALISSUES</u> [NUMC (3)]
<u>LAND1_INIT</u> [CHAR (3)]
<u>XINET_USER</u> [CHAR (1)]
<u>GUELTIGVON</u> [DATS (8)]
<u>GUELTIGVON_INPUT</u> [DATS (8)]
<u>GUELTIGBIS</u> [DATS (8)]
<u>PASSWORD_BP</u> [CHAR (40)]
<u>PASSWORD_REPEAT</u> [CHAR (40)]
<u>ZLSCH</u> [CHAR (1)]
<u>BANKS</u> [CHAR (3)]
<u>BANKL</u> [CHAR (15)]
<u>BANKN</u> [CHAR (18)]
<u>BANKA</u> [CHAR (60)]
<u>BKONT</u> [CHAR (2)]
<u>IBAN</u> [CHAR (34)]
<u>XEZER</u> [CHAR (1)]
<u>CCINS</u> [CHAR (4)]
<u>CCNUM</u> [CHAR (25)]
<u>DATBI</u> [DATS (8)]
<u>CCTYP</u> [CHAR (2)]
<u>MSGID</u> [CHAR (20)]
<u>MSGNO</u> [NUMC (3)]
<u>MSGTY</u> [CHAR (1)]
<u>MSGV1</u> [CHAR (50)]
<u>MSGV2</u> [CHAR (50)]
<u>MSGV3</u> [CHAR (50)]
<u>MSGV4</u> [CHAR (50)]
<u>ERFDAT</u> [DATS (8)]
<u>ERFTIME</u> [TIMS (6)]
<u>NATXTP</u> [CHAR (100)]
<u>JPARVW</u> [CHAR (2)]
<u>ANRED</u> [CHAR (2)]
<u>LAND1</u> [CHAR (3)]
<u>PREDIRECTIONAL</u> [CHAR (10)]
<u>POSTDIRECTIONAL</u> [CHAR (10)]
<u>SPRAS</u> [LANG (1)]
<u>REGIO</u> [CHAR (3)]
<u>KUENDGRD</u> [CHAR (3)]
<u>KEY_FIX</u> [CHAR (10)]
<u>KEY_VAR</u> [CHAR (10)]
<u>TITEL</u> [CHAR (15)]
<u>ISM_RCCVV</u> [CHAR (4)]
<u>WERBTAEAG</u> [CHAR (10)]