

SAP ABAP table JYTTRGWAER {IS-M: Trigger Entries for Currency Changes}

JYTTRGWAER-GPNR = JGTGPNR-GPNR

0..N

JGTGPNR

MANDT [CLNT (3)]

GPNR [CHAR (10)]

JYTTRGWAER-INSERTENT = JGTGPNR-GPNR

0..N

T000

MANDT [CLNT (3)]

JYTTRGWAER-MANDT = T000-MANDT

0..N

1

1

JYTTRGWAER

MANDT [CLNT (3)]

GPNR [CHAR (10)]

INSERTENT [CHAR (10)]

VKORG [CHAR (4)]

VTWEG [CHAR (2)]

SPART [CHAR (2)]

AENDATWAER [DATS (8)]

WAERS_VON [CUKY (5)]

WAERS_NACH [CUKY (5)]

KURST_NACH [CHAR (4)]

PLTYP_NACH [CHAR (2)]

JYTTRGWAER-PLTYP_NACH = T189-PLTYP

0..N

T189

MANDT [CLNT (3)]

PLTYP [CHAR (2)]

1

TCURC

MANDT [CLNT (3)]

WAERS [CUKY (5)]

JYTTRGWAER-WAERS_NACH = TCURC-WAERS

0..N

JYTTRGWAER-WAERS_VON = TCURC-WAERS

0..N

1

1

1

JYTTRGWAER-KURST_NACH = TCURV-KURST

1

TCURV

MANDT [CLNT (3)]

KURST [CHAR (4)]

JYTTRGWAER-SPART = TSPA-SPART

0..N

1

TSPA

MANDT [CLNT (3)]

SPART [CHAR (2)]

JYTTRGWAER-VKORG = TVKO-VKORG

0..N

1

1

TVKO

MANDT [CLNT (3)]

VKORG [CHAR (4)]

JYTTRGWAER-VTWEG = TVTW-VTWEG

0..N

TVTW

MANDT [CLNT (3)]

VTWEG [CHAR (2)]

0..N