

SAP ABAP table KOMKH {Batch Determination Communication Block Header}

KOMKH-HIEBO01 = KNA1-KUNNR

KOMKH-HIEBO02 = KNA1-KUNNR

KOMKH-HIEBO03 = KNA1-KUNNR

KOMKH-HIEBO04 = KNA1-KUNNR

KOMKH-HIEBO05 = KNA1-KUNNR

KOMKH-HIEBO06 = KNA1-KUNNR

KOMKH-HIEBO07 = KNA1-KUNNR

KOMKH-HIEBO08 = KNA1-KUNNR

KOMKH-HIEBO09 = KNA1-KUNNR

KOMKH-HIEBO10 = KNA1-KUNNR

KOMKH-HIEBO11 = KNA1-KUNNR

KOMKH-HIEBO12 = KNA1-KUNNR

KOMKH-HIEBO13 = KNA1-KUNNR

KOMKH-HIEBO14 = KNA1-KUNNR

KOMKH-HIEBO15 = KNA1-KUNNR

KOMKH-HIENR01 = KNA1-KUNNR

KOMKH-HIENR02 = KNA1-KUNNR

KOMKH-HIENR03 = KNA1-KUNNR

KOMKH-HIENR04 = KNA1-KUNNR

KOMKH-HIENR05 = KNA1-KUNNR

KOMKH-HIENR06 = KNA1-KUNNR

KOMKH-HIENR07 = KNA1-KUNNR

KOMKH-HIENR08 = KNA1-KUNNR

KOMKH-HIENR09 = KNA1-KUNNR

KOMKH-HIENR10 = KNA1-KUNNR

KOMKH-HIENR11 = KNA1-KUNNR

KOMKH-HIENR12 = KNA1-KUNNR

KOMKH-HIENR13 = KNA1-KUNNR

KOMKH-HIENR14 = KNA1-KUNNR

KOMKH-HIENR15 = KNA1-KUNNR

KOMKH-KNDNR = KNA1-KUNNR

KOMKH-KNRZE = KNA1-KUNNR

KOMKH-KUNNR = KNA1-KUNNR

KOMKH-KUNRE = KNA1-KUNNR

KOMKH-KUNWE = KNA1-KUNNR

KOMKH-LIFNR = LFA1-LIFNR

KOMKH-SPDNR = LFA1-LIFNR

KOMKH-MANDT = T000-MANDT

KOMKH-AUART = T0030-AUART

KOMKH-ALAND = T005-LAND1

KOMKH-LAND1 = T005-LAND1

KOMKH-COUNC = T005E-COUNC

KOMKH-CITYC = T005G-CITYC

KOMKH-REGIO = T005S-BLAND

KOMKH-WKREG = T005S-BLAND

KOMKH-EKORG = T024E-EKORG

KOMKH-KDGRP = T151-KDGRP

KOMKH-BZIRK = T171-BZIRK

KOMKH-LGNUM = T300-LGNUM

KOMKH-BWLVS = T333-BWLVS

KOMKH-INCO1 = TINC-INCO1

KOMKH-SPART = TSPA-SPART

KOMKH-AUART_SD = TVAK-AUART

KOMKH-VKBUR = TVBUR-VKBUR

KOMKH-VKGRP = TVKGR-VKGRP

KOMKH-VKORG = TVKO-VKORG

KOMKH-VSBED = TVSB-VSBED

KOMKH-VTWEG = TVTW-VTWEG

KOMKH-VBELN = VBUK-VBELN

KOMKH-POSNR = VBUP-POSNR

KOMKH	
MANDT	[CLNT (3)]
KNDNR	[CHAR (10)]
KNRZE	[CHAR (10)]
KUNRE	[CHAR (10)]
KUNWE	[CHAR (10)]
KUNNR	[CHAR (10)]
SPDNR	[CHAR (10)]
LIFNR	[CHAR (10)]
VBELN	[CHAR (10)]
POSNR	[NUMC (6)]
VKORG	[CHAR (4)]
VTWEG	[CHAR (2)]
SPART	[CHAR (2)]
EKORG	[CHAR (4)]
VKBUR	[CHAR (4)]
VKGRP	[CHAR (3)]
KDGRP	[CHAR (2)]
BZIRK	[CHAR (6)]
ALAND	[CHAR (3)]
WKREG	[CHAR (3)]
INCO1	[CHAR (3)]
LAND1	[CHAR (3)]
REGIO	[CHAR (3)]
COUNC	[CHAR (3)]
CITYC	[CHAR (4)]
AUART	[CHAR (4)]
VSBED	[CHAR (2)]
HIENR01	[CHAR (10)]
HIENR02	[CHAR (10)]
HIENR03	[CHAR (10)]
HIENR04	[CHAR (10)]
HIENR05	[CHAR (10)]
HIENR06	[CHAR (10)]
HIENR07	[CHAR (10)]
HIENR08	[CHAR (10)]
HIENR09	[CHAR (10)]
HIENR10	[CHAR (10)]
HIENR11	[CHAR (10)]
HIENR12	[CHAR (10)]
HIENR13	[CHAR (10)]
HIENR14	[CHAR (10)]
HIENR15	[CHAR (10)]
HIEBO01	[CHAR (10)]
HIEBO02	[CHAR (10)]
HIEBO03	[CHAR (10)]
HIEBO04	[CHAR (10)]
HIEBO05	[CHAR (10)]
HIEBO06	[CHAR (10)]
HIEBO07	[CHAR (10)]
HIEBO08	[CHAR (10)]
HIEBO09	[CHAR (10)]
HIEBO10	[CHAR (10)]
HIEBO11	[CHAR (10)]
HIEBO12	[CHAR (10)]
HIEBO13	[CHAR (10)]
HIEBO14	[CHAR (10)]
HIEBO15	[CHAR (10)]
LGNUM	[CHAR (3)]
BWLVS	[NUMC (3)]
AUART_SD	[CHAR (4)]

KNA1	
MANDT	[CLNT (3)]
KUNNR	[CHAR (10)]

LFA1	
MANDT	[CLNT (3)]
LIFNR	[CHAR (10)]

T000	
MANDT	[CLNT (3)]

T0030	
CLIENT	[CLNT (3)]
AUART	[CHAR (4)]

T005	
MANDT	[CLNT (3)]
LAND1	[CHAR (3)]

T005E	
MANDT	[CLNT (3)]
LAND1	[CHAR (3)]
REGIO	[CHAR (3)]
COUNC	[CHAR (3)]

T005G	
MANDT	[CLNT (3)]
LAND1	[CHAR (3)]
REGIO	[CHAR (3)]
CITYC	[CHAR (4)]

T005S	
MANDT	[CLNT (3)]
LAND1	[CHAR (3)]
BLAND	[CHAR (3)]

T024E	
MANDT	[CLNT (3)]
EKORG	[CHAR (4)]

T151	
MANDT	[CLNT (3)]
KDGRP	[CHAR (2)]

T171	
MANDT	[CLNT (3)]
BZIRK	[CHAR (6)]

T300	
MANDT	[CLNT (3)]
LGNUM	[CHAR (3)]

T333	
MANDT	[CLNT (3)]
LGNUM	[CHAR (3)]
BWLVS	[NUMC (3)]

TINC	
MANDT	[CLNT (3)]
INCO1	[CHAR (3)]

TSPA	
MANDT	[CLNT (3)]
SPART	[CHAR (2)]

TVAK	
MANDT	[CLNT (3)]
AUART	[CHAR (4)]

TVBUR	
MANDT	[CLNT (3)]
VKBUR	[CHAR (4)]

TVKGR	
MANDT	[CLNT (3)]
VKGRP	[CHAR (3)]

TVKO	
MANDT	[CLNT (3)]
VKORG	[CHAR (4)]

TVSB	
MANDT	[CLNT (3)]
VSBED	[CHAR (2)]

TVTW	
MANDT	[CLNT (3)]
VTWEG	[CHAR (2)]

VBUK	
MANDT	[CLNT (3)]
VBELN	[CHAR (10)]

VBUP	
MANDT	[CLNT (3)]
VBELN	[CHAR (10)]
POSNR	[NUMC (6)]