

SAP ABAP table KOMWBHK {Trading Contract: Communication Structure Header Data}

KOMWBHK-LCNUM = AKKP-LCNUM

| AKKP                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| LCNUM [CHAR (10)]       |

KOMWBHK-KNKLI = KNA1-KUNNR

| KNA1                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| KUNNR [CHAR (10)]       |

KOMWBHK-KUNNR = KNA1-KUNNR

| PRPS                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| PSPNR [NUMC (8)]        |

KOMWBHK-WE\_KUNNR = KNA1-KUNNR

KOMWBHK-PS\_PSP\_PNR = PRPS-PSPNR

| T000                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |

KOMWBHK-MANDT = T000-MANDT

KOMWBHK-DEFAULT\_LGORT = T001L-LGORT

| T001L                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>WERKS</u> [CHAR (4)] |
| LGORT [CHAR (4)]        |

KOMWBHK-DEFAULT\_WERKS = T001W-WERKS

| T001W                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>WERKS</u> [CHAR (4)] |

KOMWBHK-ANDTX\_SD = T005-LAND1

| T005                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>LAND1</u> [CHAR (3)] |

KOMWBHK-LANDTX = T005-LAND1

KOMWBHK-STCEG\_L = T005-LAND1

| T014                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>KKBER</u> [CHAR (4)] |

KOMWBHK-STCEG\_L\_SD = T005-LAND1

KOMWBHK-KKBER = T014-KKBER

| T024B                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>SBGRP</u> [CHAR (3)] |
| <u>KKBER</u> [CHAR (4)] |

KOMWBHK-SBGRP = T024B-SBGRP

KOMWBHK-BSARK\_SD = T176-BSARK

| T176                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>BSARK</u> [CHAR (4)] |

KOMWBHK-GRUPP = T691B-GRUPP

| T691B                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>GRUPP</u> [CHAR (4)] |
| <u>KKBER</u> [CHAR (4)] |

KOMWBHK-ABSSC = T691M-ABSSC

| T691M                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>ABSSC</u> [CHAR (6)] |

KOMWBHK-BTBSTA = TB2BA-BTBSTA

| TB2BA                    |
|--------------------------|
| <u>MANDT</u> [CLNT (3)]  |
| <u>BTBSTA</u> [CHAR (1)] |

KOMWBHK-TCTYP = TB2BE-TCTYP

| TB2BE                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>TCTYP</u> [CHAR (4)] |

KOMWBHK-LOGSYS = TBDLS-LOGSYS

| TBDLS                     |
|---------------------------|
| <u>LOGSYS</u> [CHAR (10)] |

KOMWBHK-CMWAE = TCURC-WAERS

| TCURC                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>WAERS</u> [CUKY (5)] |

KOMWBHK-SDWRS = TCURC-WAERS

KOMWBHK-TKWAERS = TCURC-WAERS

| TCURV                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>KURST</u> [CHAR (4)] |

KOMWBHK-KURST = TCURV-KURST

KOMWBHK-KURST\_SD = TCURV-KURST

KOMWBHK-PO\_STEP = TEWSTEP-STEP

| TEWSTEP                    |
|----------------------------|
| <u>MANDT</u> [CLNT (3)]    |
| <u>TEW_TYPE</u> [CHAR (4)] |
| <u>STEP</u> [CHAR (4)]     |

KOMWBHK-SO\_STEP = TEWSTEP-STEP

KOMWBHK-TC\_STEP = TEWSTEP-STEP

| TEWTCGROUP                 |
|----------------------------|
| <u>MANDT</u> [CLNT (3)]    |
| <u>TCGROUP</u> [CHAR (4)]  |
| <u>TEW_TYPE</u> [CHAR (4)] |

KOMWBHK-TCGROUP = TEWTCGROUP-TCGROUP

KOMWBHK-TEW\_TYPE = TEWTYPE-TEW\_TYPE

| TEWTYPE                    |
|----------------------------|
| <u>MANDT</u> [CLNT (3)]    |
| <u>TEW_TYPE</u> [CHAR (4)] |

KOMWBHK-KOKRS = TKA01-KOKRS

| TKA01                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>KOKRS</u> [CHAR (4)] |

KOMWBHK-LFSPG = TMFS-LFSPG

| TMFS                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>LFSPG</u> [CHAR (2)] |

KOMWBHK-AUGRU = TVAU-AUGRU

| TVAU                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>AUGRU</u> [CHAR (3)] |

KOMWBHK-VKGRP = TVBVK-VKGRP

| TVBVK                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>VKBUR</u> [CHAR (4)] |
| <u>VKGRP</u> [CHAR (3)] |

KOMWBHK-FAKSK\_SD = TVFS-FAKSP

| TVFS                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>FAKSP</u> [CHAR (2)] |

KOMWBHK-VKBUR = TVKBZ-VKBUR

| TVKBZ                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>VKORG</u> [CHAR (4)] |
| <u>VTWEG</u> [CHAR (2)] |
| <u>SPART</u> [CHAR (2)] |
| <u>VKBUR</u> [CHAR (4)] |

KOMWBHK-VKORG = TVKO-VKORG

| TVKO                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>VKORG</u> [CHAR (4)] |

KOMWBHK-VTWEG = TVKOV-VTWEG

| TVKOV                   |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>VKORG</u> [CHAR (4)] |
| <u>VTWEG</u> [CHAR (2)] |

KOMWBHK-LIFSK\_SD = TVLS-LIFSP

| TVLS                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>LIFSP</u> [CHAR (2)] |

KOMWBHK-ABRVW = TVLV-ABRVW

| TVLV                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>ABRVW</u> [CHAR (3)] |

KOMWBHK-VSBED\_SD = TVSB-VSBED

| TVSB                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>VSBED</u> [CHAR (2)] |

KOMWBHK-SPART = TVTA-SPART

| TVTA                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>VKORG</u> [CHAR (4)] |
| <u>VTWEG</u> [CHAR (2)] |
| <u>SPART</u> [CHAR (2)] |

KOMWBHK-KVGR1\_SD = TVV1-KVGR1

| TVV1                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>KVGR1</u> [CHAR (3)] |

KOMWBHK-KVGR2\_SD = TVV2-KVGR2

| TVV2                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>KVGR2</u> [CHAR (3)] |

KOMWBHK-KVGR3\_SD = TVV3-KVGR3

| TVV3                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>KVGR3</u> [CHAR (3)] |

KOMWBHK-KVGR4\_SD = TVV4-KVGR4

| TVV4                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>KVGR4</u> [CHAR (3)] |

KOMWBHK-KVGR5\_SD = TVV5-KVGR5

| TVV5                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>KVGR5</u> [CHAR (3)] |

| KOMWBHK                         |
|---------------------------------|
| <u>MANDT</u> [CLNT (3)]         |
| <u>TCTYP</u> [CHAR (4)]         |
| <u>KUNNR</u> [CHAR (10)]        |
| <u>BTBSTA</u> [CHAR (1)]        |
| <u>TKWAERS</u> [CUKY (5)]       |
| <u>VKORG</u> [CHAR (4)]         |
| <u>VTWEG</u> [CHAR (2)]         |
| <u>SPART</u> [CHAR (2)]         |
| <u>SDWRS</u> [CUKY (5)]         |
| <u>KURST_SD</u> [CHAR (4)]      |
| <u>KURST</u> [CHAR (4)]         |
| <u>AUGRU</u> [CHAR (3)]         |
| <u>ABSSC</u> [CHAR (6)]         |
| <u>LCNUM</u> [CHAR (10)]        |
| <u>LOGSYS</u> [CHAR (10)]       |
| <u>LIFSK_SD</u> [CHAR (2)]      |
| <u>FAKSK_SD</u> [CHAR (2)]      |
| <u>VKGRP</u> [CHAR (3)]         |
| <u>VKBUR</u> [CHAR (4)]         |
| <u>VSBED_SD</u> [CHAR (2)]      |
| <u>BSARK_SD</u> [CHAR (4)]      |
| <u>STCEG_L_SD</u> [CHAR (3)]    |
| <u>ANDTX_SD</u> [CHAR (3)]      |
| <u>KVGR1_SD</u> [CHAR (3)]      |
| <u>KVGR2_SD</u> [CHAR (3)]      |
| <u>KVGR3_SD</u> [CHAR (3)]      |
| <u>KVGR4_SD</u> [CHAR (3)]      |
| <u>KVGR5_SD</u> [CHAR (3)]      |
| <u>KOKRS</u> [CHAR (4)]         |
| <u>KKBER</u> [CHAR (4)]         |
| <u>KNKLI</u> [CHAR (10)]        |
| <u>GRUPP</u> [CHAR (4)]         |
| <u>SBGRP</u> [CHAR (3)]         |
| <u>CTLPC</u> [CHAR (3)]         |
| <u>CMWAE</u> [CUKY (5)]         |
| <u>LFSPG</u> [CHAR (2)]         |
| <u>WE_KUNNR</u> [CHAR (10)]     |
| <u>STCEG_L</u> [CHAR (3)]       |
| <u>LANDTX</u> [CHAR (3)]        |
| <u>TEW_TYPE</u> [CHAR (4)]      |
| <u>ABRVW</u> [CHAR (3)]         |
| <u>PS_PSP_PNR</u> [NUMC (8)]    |
| <u>DEFAULT_WERKS</u> [CHAR (4)] |
| <u>DEFAULT_LGORT</u> [CHAR (4)] |
| <u>TCGROUP</u> [CHAR (4)]       |
| <u>SO_STEP</u> [CHAR (4)]       |
| <u>PO_STEP</u> [CHAR (4)]       |
| <u>TC_STEP</u> [CHAR (4)]       |