

SAP ABAP table MASS_MARC_D {mass maintenance structure for MARC data}

	MASS_MARC_D-VSO/R PKGRP = /VSO/M_PKG-PKGRP	0..N	_VSO_M_PKG MANDT [CLNT (3)] WERKS [CHAR (4)] PKGRP [CHAR (18)]
	MASS_MARC_D-VSO/R PKGRP MO = /VSO/M_PKG-PKGRP	0..N	
	MASS_MARC_D-KUNNR W = KNA1-KUNNR	0..N	KNA1 MANDT [CLNT (3)] KUNNR [CHAR (10)]
	MASS_MARC_D-KUNNR WO = KNA1-KUNNR	0..N	
	MASS_MARC_D-MATNR = MARA-MATNR	0..N	MARA MANDT [CLNT (3)] MATNR [CHAR (18)]
	MASS_MARC_D-MATNR MO = MARA-MATNR	0..N	
	MASS_MARC_D-MATNR P = MARA-MATNR	0..N	
	MASS_MARC_D-MATNR PO = MARA-MATNR	0..N	
	MASS_MARC_D-MATNR W = MARA-MATNR	0..N	
	MASS_MARC_D-MATNR WO = MARA-MATNR	0..N	
	MASS_MARC_D-NFMAT = MARA-MATNR	0..N	
	MASS_MARC_D-NFMAT MO = MARA-MATNR	0..N	
	MASS_MARC_D-STDPD = MARA-MATNR	0..N	
	MASS_MARC_D-STDPD MO = MARA-MATNR	0..N	
	MASS_MARC_D-UCMAT = MARA-MATNR	0..N	
	MASS_MARC_D-UCMAT MO = MARA-MATNR	0..N	
	MASS_MARC_D-VRBMT = MARA-MATNR	0..N	
	MASS_MARC_D-VRBMT MO = MARA-MATNR	0..N	
	MASS_MARC_D-DISPR = MDIP-DISPR	0..N	MDIP MANDT [CLNT (3)] DISPR [CHAR (4)]
	MASS_MARC_D-DISPR MO = MDIP-DISPR	0..N	
	MASS_MARC_D-PROPR P = MPRP-PROPR	0..N	MPRP MANDT [CLNT (3)] PROPR [CHAR (4)]
	MASS_MARC_D-PROPR PO = MPRP-PROPR	0..N	
	MASS_MARC_D-UMRSL = OIB01-UMRSL	0..N	OIB01 MANDT [CLNT (3)] UMRSL [CHAR (4)]
	MASS_MARC_D-UMRSL MO = OIB01-UMRSL	0..N	
	MASS_MARC_D-UOMGR = OIB06-UOMGR	0..N	OIB06 MANDT [CLNT (3)] UOMGR [CHAR (3)]
	MASS_MARC_D-UOMGR MO = OIB06-UOMGR	0..N	
	MASS_MARC_D-VSPVB = PVBE-PRVBE	0..N	PVBE MANDT [CLNT (3)] WERKS [CHAR (4)] PRVBE [CHAR (10)]
	MASS_MARC_D-VSPVB MO = PVBE-PRVBE	0..N	
	MASS_MARC_D-RDPRF = RDPR-RDPRF	0..N	RDPR MANDT [CLNT (3)] WERKS [CHAR (4)] RDPRF [CHAR (4)] RDZAE [NUMC (6)]
	MASS_MARC_D-RDPRF MO = RDPR-RDPRF	0..N	
	MASS_MARC_D-MANDT = T000-MANDT	0..N	T000 MANDT [CLNT (3)]
	MASS_MARC_D-MANDT MO = T000-MANDT	0..N	
	MASS_MARC_D-MANDT P = T000-MANDT	0..N	
	MASS_MARC_D-MANDT PO = T000-MANDT	0..N	
	MASS_MARC_D-MANDT W = T000-MANDT	0..N	
	MASS_MARC_D-MANDT WO = T000-MANDT	0..N	
	MASS_MARC_D-LGFSB = T001L-LGORT	0..N	T001L MANDT [CLNT (3)] WERKS [CHAR (4)] LGORT [CHAR (4)]
	MASS_MARC_D-LGFSB MO = T001L-LGORT	0..N	
	MASS_MARC_D-LGPRO = T001L-LGORT	0..N	
	MASS_MARC_D-LGPRO MO = T001L-LGORT	0..N	
	MASS_MARC_D-VRBWK = T001W-WERKS	0..N	T001W MANDT [CLNT (3)] WERKS [CHAR (4)]
	MASS_MARC_D-VRBWK MO = T001W-WERKS	0..N	
	MASS_MARC_D-WERKS = T001W-WERKS	0..N	
	MASS_MARC_D-WERKS MO = T001W-WERKS	0..N	
	MASS_MARC_D-WERKS P = T001W-WERKS	0..N	
	MASS_MARC_D-WERKS PO = T001W-WERKS	0..N	
	MASS_MARC_D-HERKL = T005-LAND1	0..N	T005 MANDT [CLNT (3)] LAND1 [CHAR (3)]
	MASS_MARC_D-HERKL MO = T005-LAND1	0..N	
	MASS_MARC_D-HERKR = T005S-BLAND	0..N	T005S MANDT [CLNT (3)] LAND1 [CHAR (3)] BLAND [CHAR (3)]
	MASS_MARC_D-HERKR MO = T005S-BLAND	0..N	
	MASS_MARC_D-AUSME = T006-MSEHI	0..N	T006 MANDT [CLNT (3)] MSEHI [UNIT (3)]
	MASS_MARC_D-AUSME MO = T006-MSEHI	0..N	
	MASS_MARC_D-EXPME = T006-MSEHI	0..N	
	MASS_MARC_D-EXPME MO = T006-MSEHI	0..N	
	MASS_MARC_D-FRTME = T006-MSEHI	0..N	
	MASS_MARC_D-FRTME MO = T006-MSEHI	0..N	
	MASS_MARC_D-LZEIH = T006-MSEHI	0..N	
	MASS_MARC_D-LZEIH MO = T006-MSEHI	0..N	
	MASS_MARC_D-PERIV = T009-PERIV	0..N	T024 MANDT [CLNT (3)] EKGRP [CHAR (3)]
	MASS_MARC_D-PERIV MO = T009-PERIV	0..N	
	MASS_MARC_D-EKGRP = T024-EKGRP	0..N	T024D MANDT [CLNT (3)] WERKS [CHAR (4)] DISPO [CHAR (3)]
	MASS_MARC_D-EKGRP MO = T024-EKGRP	0..N	
	MASS_MARC_D-DISPO = T024D-DISPO	0..N	T024F MANDT [CLNT (3)] WERKS [CHAR (4)] FEVOR [CHAR (3)]
	MASS_MARC_D-DISPO MO = T024D-DISPO	0..N	
	MASS_MARC_D-FEVOR = T024F-FEVOR	0..N	T141 MANDT [CLNT (3)] MMSTA [CHAR (2)]
	MASS_MARC_D-FEVOR MO = T024F-FEVOR	0..N	
	MASS_MARC_D-MMSTA = T141-MMSTA	0..N	T149C MANDT [CLNT (3)] BWTTY [CHAR (1)]
	MASS_MARC_D-MMSTA MO = T141-MMSTA	0..N	
	MASS_MARC_D-BWTTY = T149C-BWTTY	0..N	T159C MANDT [CLNT (3)] WERKS [CHAR (4)] ABGIN [CHAR (1)]
	MASS_MARC_D-BWTTY MO = T149C-BWTTY	0..N	
	MASS_MARC_D-ABGIN = T159C-ABGIN	0..N	T377P MANDT [CLNT (3)] SERAIL [CHAR (4)]
	MASS_MARC_D-SERNP = T377P-SERAIL	0..N	
	MASS_MARC_D-SERNP MO = T377P-SERAIL	0..N	
	MASS_MARC_D-STLAN = T416-STLAN	0..N	T434G MANDT [CLNT (3)] WERKS [CHAR (4)] EPRIQ [CHAR (4)]
	MASS_MARC_D-STLAN MO = T416-STLAN	0..N	
	MASS_MARC_D-EPRIO = T434G-EPRIO	0..N	T436A MANDT [CLNT (3)] WERKS [CHAR (4)] FHORI [CHAR (3)]
	MASS_MARC_D-EPRIO MO = T434G-EPRIO	0..N	
	MASS_MARC_D-FHORI = T436A-FHORI	0..N	
	MASS_MARC_D-FHORI MO = T436A-FHORI	0..N	
	MASS_MARC_D-SFEPR = T437S-SFPRO	0..N	T437S MANDT [CLNT (3)] SFPRO [CHAR (4)]
	MASS_MARC_D-SFEPR MO = T437S-SFPRO	0..N	
	MASS_MARC_D-DISMM = T438A-DISMM	0..N	T438A MANDT [CLNT (3)] DISMM [CHAR (2)]
	MASS_MARC_D-DISMM MO = T438A-DISMM	0..N	
	MASS_MARC_D-DISMM W = T438A-DISMM	0..N	T438M MANDT [CLNT (3)] WERKS [CHAR (4)] MTART [CHAR (4)]
	MASS_MARC_D-DISMM WO = T438A-DISMM	0..N	
	MASS_MARC_D-DISGR = T438M-MTART	0..N	T438R MANDT [CLNT (3)] WERKS [CHAR (4)] RWPRO [CHAR (3)]
	MASS_MARC_D-DISGR MO = T438M-MTART	0..N	
	MASS_MARC_D-RWPRO = T438R-RWPRO	0..N	
	MASS_MARC_D-RWPRO MO = T438R-RWPRO	0..N	
	MASS_MARC_D-SHPRO = T438V-SHPRO	0..N	T438V MANDT [CLNT (3)] WERKS [CHAR (4)] SHPRO [CHAR (3)]
	MASS_MARC_D-SHPRO MO = T438V-SHPRO	0..N	
	MASS_MARC_D-DISLS = T439A-DISLS	0..N	T439A MANDT [CLNT (3)] DISLS [CHAR (2)]
	MASS_MARC_D-DISLS MO = T439A-DISLS	0..N	
	MASS_MARC_D-LFRHY = T439G-MRPPP	0..N	T439G MANDT [CLNT (3)] WERKS [CHAR (4)] MRPPP [CHAR (3)]
	MASS_MARC_D-LFRHY MO = T439G-MRPPP	0..N	
	MASS_MARC_D-MRPPP = T439G-MRPPP	0..N	T439L MANDT [CLNT (3)] WERKS [CHAR (4)] LAGPR [CHAR (1)]
	MASS_MARC_D-MRPPP MO = T439G-MRPPP	0..N	
	MASS_MARC_D-LAGPR = T439L-LAGPR	0..N	
	MASS_MARC_D-LAGPR MO = T439L-LAGPR	0..N	
	MASS_MARC_D-AUFTL = T439P-AUFTL	0..N	T439P MANDT [CLNT (3)] WERKS [CHAR (4)] PERKZ [CHAR (1)] AUFTL [CHAR (1)]
	MASS_MARC_D-AUFTL MO = T439P-AUFTL	0..N	
	MASS_MARC_D-SOBSL = T460A-SOBSL	0..N	T460A MANDT [CLNT (3)] WERKS [CHAR (4)] SOBSL [CHAR (2)]
	MASS_MARC_D-SOBSK = T460A-SOBSL	0..N	
	MASS_MARC_D-SOBSL = T460A-SOBSL	0..N	T461P MANDT [CLNT (3)] STRGR [CHAR (2)]
	MASS_MARC_D-SOBSL MO = T460A-SOBSL	0..N	
	MASS_MARC_D-STRGR = T461P-STRGR	0..N	T46AC MANDT [CLNT (3)] MDACH [CHAR (2)] ACCFM [CHAR (4)] ACCTQ [CHAR (4)]
	MASS_MARC_D-STRGR MO = T461P-STRGR	0..N	
	MASS_MARC_D-MDACH = T46AC-MDACH	0..N	
	MASS_MARC_D-MDACH MO = T46AC-MDACH	0..N	
	MASS_MARC_D-STAWN = T604-STAWN	0..N	T604 MANDT [CLNT (3)] LANDI [CHAR (3)] STAWN [CHAR (17)]
	MASS_MARC_D-STAWN MO = T604-STAWN	0..N	
	MASS_MARC_D-STEUC = T604F-STEUC	0..N	T604F MANDT [CLNT (3)] LANDI [CHAR (3)] STEUC [CHAR (16)]
	MASS_MARC_D-STEUC MO = T604F-STEUC	0..N	
	MASS_MARC_D-GPNUM = T609G-GPNUM	0..N	T609G MANDT [CLNT (3)] LANDI [CHAR (3)] GPNUM [CHAR (9)]
	MASS_MARC_D-GPNUM MO = T609G-GPNUM	0..N	
	MASS_MARC_D-CASNR = T610C-CASNR	0..N	T610C MANDT [CLNT (3)] LANDI [CHAR (3)] CASNR [CHAR (15)]
	MASS_MARC_D-CASNR MO = T610C-CASNR	0..N	
	MASS_MARC_D-MOGRU = T618G-MOGRU	0..N	T618G MANDT [CLNT (3)] LANDI [CHAR (3)] MOGRU [CHAR (6)]
	MASS_MARC_D-MOGRU MO = T618G-MOGRU	0..N	
	MASS_MARC_D-MOWNR = T618M-MOWNR	0..N	T618M MANDT [CLNT (3)] LANDI [CHAR (3)] MOWNR [CHAR (12)]
	MASS_MARC_D-MOWNR MO = T618M-MOWNR	0..N	
	MASS_MARC_D-OTYPE = T778O-OTYPE	0..N	T778O MANDT [CLNT (3)] QTYPE [CHAR (2)]
	MASS_MARC_D-OTYPE MO = T778O-OTYPE	0..N	
	MASS_MARC_D-PLVAR = T778P-PLVAR	0..N	T778P MANDT [CLNT (3)] PLVAR [CHAR (2)]
	MASS_MARC_D-PLNTY = TCA01-PLNTY	0..N	TCA01 MANDT [CLNT (3)] PLNTY [CHAR (1)]
	MASS_MARC_D-PLNTY MO = TCA01-PLNTY	0..N	
	MASS_MARC_D-SFCPF = TCO43-CO_PRODPRF	0..N	TCO43 MANDT [CLNT (3)] WERKS [CHAR (4)] CO_PRODPRF [CHAR (6)]
	MASS_MARC_D-SFCPF MO = TCO43-CO_PRODPRF	0..N	
	MASS_MARC_D-OCMPF = TCO48-GPROFILE	0..N	TCO48 MANDT [CLNT (3)] GPROFILE [CHAR (6)]
	MASS_MARC_D-OCMPF MO = TCO48-GPROFILE	0..N	
	MASS_MARC_D-COMPL = TCSCP_COMP_LVL-COMP_LEVEL	0..N	TCSCP_COMP_LVL MANDT [CLNT (3)] COMP_LEVEL [NUMC (2)]
	MASS_MARC_D-COMPL MO = TCSCP_COMP_LVL-COMP_LEVEL	0..N	
	MASS_MARC_D-CONVT = TCSCP_CONV_TYPE-CONV_TYPE	0..N	TCSCP_CONV_TYPE MANDT [CLNT (3)] CONV_TYPE [CHAR (2)]
	MASS_MARC_D-CONVT MO = TCSCP_CONV_TYPE-CONV_TYPE	0..N	
	MASS_MARC_D-IUID_TYPE = TIUID_TYPE-IUID_TYPE	0..N	TIUID_TYPE IUID_TYPE [CHAR (10)]
	MASS_MARC_D-IUID_TYPE MO = TIUID_TYPE-IUID_TYPE	0..N	
	MASS_MARC_D-AWSLS = TKV01-AWSLS	0..N	TKV01 MANDT [CLNT (3)] AWOBA [CHAR (2)] AWSLS [CHAR (6)]
	MASS_MARC_D-AWSLS MO = TKV01-AWSLS	0..N	
	MASS_MARC_D-LADGR = TLGR-LADGR	0..N	TLGR MANDT [CLNT (3)] LADGR [CHAR (4)]
	MASS_MARC_D-LADGR MO = TLGR-LADGR	0..N	
	MASS_MARC_D-LOGGR = TLOG-LOGGR	0..N	TLOG MANDT [CLNT (3)] LOGGR [CHAR (4)]
	MASS_MARC_D-LOGGR MO = TLOG-LOGGR	0..N	
	MASS_MARC_D-MAABC = TMABC-MAABC	0..N	TMABC MANDT [CLNT (3)] MAABC [CHAR (1)]
	MASS_MARC_D-MAABC MO = TMABC-MAABC	0..N	
	MASS_MARC_D-BWSCL = TMBW1-BWSCL	0..N	TMBW1 MANDT [CLNT (3)] BWSCL [CHAR (1)]
	MASS_MARC_D-BWSCL MO = TMBW1-BWSCL	0..N	
	MASS_MARC_D-MFRGR = TMFG-MFRGR	0..N	TMFG MANDT [CLNT (3)] MFRGR [CHAR (8)]
	MASS_MARC_D-MFRGR MO = TMFG-MFRGR	0..N	
	MASS_MARC_D-FPRFM = TMFPF-FPRFM	0..N	TMFPF MANDT [CLNT (3)] EPREM [CHAR (3)]
	MASS_MARC_D-FPRFM MO = TMFPF-FPRFM	0..N	
	MASS_MARC_D-USEQU = TMQ2-USEQU	0..N	TMQ2 MANDT [CLNT (3)] USEQU [CHAR (1)]
	MASS_MARC_D-USEQU MO = TMQ2-USEQU	0..N	
	MASS_MARC_D-MTVFP = TMVF-MTVFP	0..N	TMVF MANDT [CLNT (3)] MTVFP [CHAR (2)]
	MASS_MARC_D-MTVFP MO = TMVF-MTVFP	0..N	
	MASS_MARC_D-QMATA = TQ01B-QMATAUTH	0..N	TQ01B MANDT [CLNT (3)] QMATAUTH [CHAR (6)]
	MASS_MARC_D-QMATA MO = TQ01B-QMATAUTH	0..N	
	MASS_MARC_D-QSSYS = TQ02-QSSYS	0..N	TQ02 MANDT [CLNT (3)] QSSYS [CHAR (4)]
	MASS_MARC_D-QSSYS MO = TQ02-QSSYS	0..N	
	MASS_MARC_D-QZGTP = TQ05-ZGTYP	0..N	TQ05 MANDT [CLNT (3)] ZGTYP [CHAR (4)]
	MASS_MARC_D-QZGTP MO = TQ05-ZGTYP	0..N	
	MASS_MARC_D-SSQSS = TQ08-QM_PUR	0..N	TQ08 MANDT [CLNT (3)] QM_PUR [CHAR (8)]
	MASS_MARC_D-SSQSS MO = TQ08-QM_PUR	0..N	
	MASS_MARC_D-MTVER = TVFM-MTVER	0..N	TVFM MANDT [CLNT (3)] MTVER [CHAR (4)]
	MASS_MARC_D-MTVER MO = TVFM-MTVER	0..N	
	MASS_MARC_D-MEGRU = TWMEG-MEGRU	0..N	TWMEG MANDT [CLNT (3)] MEGRU [CHAR (4)] ME/MS [UNIT (3)]
	MASS_MARC_D-MEGRU MO = TWMEG-MEGRU	0..N	
	MASS_MARC_D-SERVG = TWSG-SERVG	0..N	TWSG MANDT [CLNT (3)] SERVG [CHAR (1)]
	MASS_MARC_D-SERVG MO = TWSG-SERVG	0..N	
	MASS_MARC_D-CONS_PROCG = WRF_T CONS_PROCG-WRF CONS_PROCG	0..N	WRF_T CONS_PROCG MANDT [CLNT (3)] WRF_CONS_PROCG [CHAR (1)]
	MASS_MARC_D-CONS_PROCG MO = WRF_T CONS_PROCG-WRF CONS_PROCG	0..N	
	MASS_MARC_D-REF_SCHEMA = WRF_REF_RFS-REF_SCHEMA	0..N	WRF_REF_RFS MANDT [CLNT (3)] REF_SCHEMA [CHAR (2)]
	MASS_MARC_D-REF_SCHEMA MO = WRF_REF_RFS-REF_SCHEMA	0..N	