

SAP ABAP table MASSQUOTHEAD {Generated Table for View}

MASSQUOTHEAD-FFPRF = AD01C_PROF-PROFN

AD01C_PROF
MANDT [CLNT (3)]
PROFN [NUMC (8)]
DPU [NUMC (4)]

MASSQUOTHEAD-LCNUM = AKKP-LCNUM

AKKP
MANDT [CLNT (3)]
LCNUM [CHAR (10)]

MASSQUOTHEAD-AUFNR = AUFK-AUFNR

AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

MASSQUOTHEAD-FPLNR = FPLA-FPLNR

FPLA
MANDT [CLNT (3)]
FPLNR [CHAR (10)]

MASSQUOTHEAD-RPLNR = FPLA-FPLNR

J_1ADTYP
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
J_1ADTYP [CHAR (2)]

MASSQUOTHEAD-J_1ADTYP = J_1ADTYP-J_1ADTYP

J_1AFITP
MANDT [CLNT (3)]
KOART [CHAR (1)]
J_1AFITP [CHAR (2)]

MASSQUOTHEAD-J_1AFITP = J_1AFITP-J_1AFITP

J_1AGICD
MANDT [CLNT (3)]
LANDI [CHAR (3)]
J_1AGICD [CHAR (2)]

MASSQUOTHEAD-J_1AGICD = J_1AGICD-J_1AGICD

J_1AINFT20
MANDT [CLNT (3)]
J_1AINDX [CHAR (5)]

MASSQUOTHEAD-J_1AINDX = J_1AINFT20-J_1AINDX

J_1ARFZ
MANDT [CLNT (3)]
J_1ARFZ [CHAR (1)]

MASSQUOTHEAD-J_1ARFZ = J_1ARFZ-J_1ARFZ

J_1ATXREL
MANDT [CLNT (3)]
J_1ATXREL [CHAR (10)]

MASSQUOTHEAD-J_1ATXREL = J_1ATXREL-J_1ATXREL

KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]

MASSQUOTHEAD-KNKLI = KNA1-KUNNR

KONA
MANDT [CLNT (3)]
KNUMA [CHAR (10)]

MASSQUOTHEAD-KUNNR = KNA1-KUNNR

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

MASSQUOTHEAD-KNUMA = KONA-KNUMA

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

MASSQUOTHEAD-TRMTYP = MARA-MATNR

ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]

MASSQUOTHEAD-OBJNR = ONR00-OBJNR

PRPS
MANDT [CLNT (3)]
PSPNR [NUMC (8)]

MASSQUOTHEAD-PS_PSP_PNR = PRPS-PSPNR

QMEL
MANDT [CLNT (3)]
QMNUM [CHAR (12)]

MASSQUOTHEAD-QMNUM = QMEL-QMNUM

T000
MANDT [CLNT (3)]

MASSQUOTHEAD-MANDT = T000-MANDT

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

MASSQUOTHEAD-BUKRS_VF = T001-BUKRS

T005
MANDT [CLNT (3)]
LANDI [CHAR (3)]

MASSQUOTHEAD-LANDTX = T005-LANDI

T005S
MANDT [CLNT (3)]
LANDI [CHAR (3)]
BLAND [CHAR (3)]

MASSQUOTHEAD-STCEG_L = T005-LANDI

T014
MANDT [CLNT (3)]
KKBER [CHAR (4)]

MASSQUOTHEAD-J_1AREGIO = T005S-BLAND

T024B
MANDT [CLNT (3)]
SBGRP [CHAR (3)]
KKBER [CHAR (4)]

MASSQUOTHEAD-KKBER = T014-KKBER

T040
MANDT [CLNT (3)]
MSCHL [CHAR (1)]

MASSQUOTHEAD-SBGRP = T024B-SBGRP

T040S
MANDT [CLNT (3)]
MANS [CHAR (1)]

MASSQUOTHEAD-MSCHL = T040-MSCHL

T042Z
MANDT [CLNT (3)]
LANDI [CHAR (3)]
ZLSCH [CHAR (1)]

MASSQUOTHEAD-MANS = T040S-MANS

T042Z
MANDT [CLNT (3)]
LANDI [CHAR (3)]
ZLSCH [CHAR (1)]

MASSQUOTHEAD-ZLSCH = T042Z-ZLSCH

T151
MANDT [CLNT (3)]
KDGRP [CHAR (2)]

MASSQUOTHEAD-KDGRP = T151-KDGRP

T171
MANDT [CLNT (3)]
BZIRK [CHAR (6)]

MASSQUOTHEAD-BZIRK = T171-BZIRK

T173
MANDT [CLNT (3)]
VSART [CHAR (2)]

MASSQUOTHEAD-VSART = T173-VSART

T176
MANDT [CLNT (3)]
BSARK [CHAR (4)]

MASSQUOTHEAD-BSARK = T176-BSARK

T188
MANDT [CLNT (3)]
KONDA [CHAR (2)]

MASSQUOTHEAD-BSARK_E = T176-BSARK

T189
MANDT [CLNT (3)]
PLTYP [CHAR (2)]

MASSQUOTHEAD-KONDA = T188-KONDA

T683
MANDT [CLNT (3)]
KVEWE [CHAR (1)]
KAPPL [CHAR (2)]
KALSM [CHAR (6)]

MASSQUOTHEAD-PLTYP = T189-PLTYP

T691A
MANDT [CLNT (3)]
CTLPC [CHAR (3)]
KKBER [CHAR (4)]

MASSQUOTHEAD-KALSM = T683-KALSM

T691M
MANDT [CLNT (3)]
ABSSC [CHAR (6)]

MASSQUOTHEAD-KALSM_CH = T683-KALSM

TBMOT
MANDT [CLNT (3)]
BEMOT [CHAR (2)]

MASSQUOTHEAD-CTLPC = T691A-CTLPC

TCURC
MANDT [CLNT (3)]
WAERS [CHAR (5)]

MASSQUOTHEAD-ABSSC = T691M-ABSSC

TCURV
MANDT [CLNT (3)]
KURST [CHAR (4)]

MASSQUOTHEAD-BEMOT = TBMOT-BEMOT

TDGC5
MANDT [CLNT (3)]
PROLI [CHAR (3)]

MASSQUOTHEAD-AKWAE = TCURC-WAERS

TFACD
IDENT [CHAR (2)]

MASSQUOTHEAD-CMWAE = TCURC-WAERS

TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]

MASSQUOTHEAD-STWAE = TCURC-WAERS

THIT
MANDT [CLNT (3)]
HITYP [CHAR (1)]

MASSQUOTHEAD-WAERK = TCURC-WAERS

TINC
MANDT [CLNT (3)]
INCO1 [CHAR (3)]

MASSQUOTHEAD-WKWAE = TCURC-WAERS

TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]

MASSQUOTHEAD-KURST = TCURV-KURST

TSAB
MANDT [CLNT (3)]
ABTNR [CHAR (4)]

MASSQUOTHEAD-PROLI = TDGC5-PROLI

TVAK
MANDT [CLNT (3)]
AUART [CHAR (4)]

MASSQUOTHEAD-PERRL = TFACD-IDENT

TVAU
MANDT [CLNT (3)]
AUGRU [CHAR (3)]

MASSQUOTHEAD-GSBER = TGSB-GSBER

TVBKV
MANDT [CLNT (3)]
KVBUR [CHAR (4)]
KVGRP [CHAR (3)]

MASSQUOTHEAD-GSKST = TGSB-GSBER

TVDC
MANDT [CLNT (3)]
DELCO [CHAR (3)]

MASSQUOTHEAD-WAKTION = TVGRPS-SCHEME

TVFK
MANDT [CLNT (3)]
EKART [CHAR (4)]

MASSQUOTHEAD-HITYP_PR = THIT-HITYP

TVFS
MANDT [CLNT (3)]
FAKSP [CHAR (2)]

MASSQUOTHEAD-INCO1 = TINC-INCO1

TVGRPS
MANDT [CLNT (3)]
SCHEME [CHAR (4)]

MASSQUOTHEAD-KOKRS = TKA01-KOKRS

TVKBZ
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]
KVBUR [CHAR (4)]

MASSQUOTHEAD-ABTNR = TSAB-ABTNR

TVKGG
MANDT [CLNT (3)]
KDKG1 [CHAR (2)]
KDKG2 [CHAR (2)]
KDKG3 [CHAR (2)]
KDKG4 [CHAR (2)]
KDKG5 [CHAR (2)]

MASSQUOTHEAD-AUART = TVAK-AUART

TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]

MASSQUOTHEAD-AUGRU = TVAU-AUGRU

TVKOV
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]

MASSQUOTHEAD-VKGRP = TVBKV-KVBUR

TVKT
MANDT [CLNT (3)]
KTGRD [CHAR (2)]

MASSQUOTHEAD-KDKG1 = TVKGG-KDKGR

TVLS
MANDT [CLNT (3)]
LIFSP [CHAR (2)]

MASSQUOTHEAD-KDKG2 = TVKGG-KDKGR

TVLV
MANDT [CLNT (3)]
ABRVW [CHAR (3)]

MASSQUOTHEAD-KDKG3 = TVKGG-KDKGR

TVSAK
MANDT [CLNT (3)]
SDABW [CHAR (4)]

MASSQUOTHEAD-KDKG4 = TVKGG-KDKGR

TVSB
MANDT [CLNT (3)]
VSBED [CHAR (2)]

MASSQUOTHEAD-KDKG5 = TVKGG-KDKGR

TVTA
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]

MASSQUOTHEAD-VKORG = TVKO-VKORG

TVTY
MANDT [CLNT (3)]
TRATY [CHAR (4)]

MASSQUOTHEAD-VTWEG = TVKOV-VTWEG

TVV1
MANDT [CLNT (3)]
KVGR1 [CHAR (3)]

MASSQUOTHEAD-KTGRD = TVKT-KTGRD

TVV2
MANDT [CLNT (3)]
KVGR2 [CHAR (3)]

MASSQUOTHEAD-LIFSK = TVLS-LIFSP

TVV3
MANDT [CLNT (3)]
KVGR3 [CHAR (3)]

MASSQUOTHEAD-ABRVW = TVLV-ABRVW

TVV4
MANDT [CLNT (3)]
KVGR4 [CHAR (3)]

MASSQUOTHEAD-SDABW = TVSAK-SDABW

TVV5
MANDT [CLNT (3)]
KVGR5 [CHAR (3)]

MASSQUOTHEAD-VSBED = TVSB-VSBED

VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]

MASSQUOTHEAD-SPART = TVTA-SPART

WAKH
MANDT [CLNT (3)]
AKTNR [CHAR (10)]

MASSQUOTHEAD-TRATY = TVTY-TRATY

WWMI
MANDT [CLNT (3)]
WMINR [CHAR (10)]

MASSQUOTHEAD-KVGR1 = TVV1-KVGR1

MASSQUOTHEAD-KVGR2 = TVV2-KVGR2

MASSQUOTHEAD-KVGR3 = TVV3-KVGR3

MASSQUOTHEAD-KVGR4 = TVV4-KVGR4

MASSQUOTHEAD-KVGR5 = TVV5-KVGR5

MASSQUOTHEAD-VBELN = VBUK-VBELN

MASSQUOTHEAD-VBUP = VBUK-VBELN

MASSQUOTHEAD-POSNR = VBUP-POSNR

MASSQUOTHEAD-WMINR = WWMI-WMINR

MASSQUOTHEAD
MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]
AUART [CHAR (4)]
AUGRU [CHAR (3)]
LIFSK [CHAR (2)]
FAKSK [CHAR (2)]
WAERK [CUKY (5)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]
VKGRP [CHAR (3)]
VKBUR [CHAR (4)]
GSBER [CHAR (4)]
GSKST [CHAR (4)]
KALSM [CHAR (6)]
VSBED [CHAR (2)]
FKARA [CHAR (4)]
KUNNR [CHAR (10)]
STWAE [CUKY (5)]
KVGR1 [CHAR (3)]
KVGR2 [CHAR (3)]
KVGR3 [CHAR (3)]
KVGR4 [CHAR (3)]
KVGR5 [CHAR (3)]
KNUMA [CHAR (10)]
KOKRS [CHAR (4)]
PS_PSP_PNR [NUMC (8)]
KURST [CHAR (4)]
KKBER [CHAR (4)]
KNKLI [CHAR (10)]
SBGRP [CHAR (3)]
CTLPC [CHAR (3)]
CMWAE [CUKY (5)]
HITYP_PR [CHAR (1)]
ABRVW [CHAR (3)]
VGBEL [CHAR (10)]
OBJNR [CHAR (22)]
BUKRS_VF [CHAR (4)]
KALSM_CH [CHAR (6)]
AUFNR [CHAR (12)]
QMNUM [CHAR (12)]
SCHEME_GRP [CHAR (4)]
RPLNR [CHAR (10)]
STCEG_L [CHAR (3)]
LANDTX [CHAR (3)]
KONDA [CHAR (2)]
KDGRP [CHAR (2)]
BZIRK [CHAR (6)]
INCO1 [CHAR (3)]
PERFK [CHAR (2)]
PERRL [CHAR (2)]
ZLSCH [CHAR (1)]
KTGRD [CHAR (2)]
MSCHL [CHAR (1)]
MANS [CHAR (1)]
FPLNR [CHAR (10)]
WAKTION [CHAR (10)]
ABSSC [CHAR (6)]
LCNUM [CHAR (10)]
J_1AFITP [CHAR (2)]
J_1ARFZ [CHAR (1)]
J_1AGICD [CHAR (2)]
J_1ADTYP [CHAR (2)]
J_1ATXREL [CHAR (10)]
ABTNR [CHAR (4)]
BSARK [CHAR (4)]
BSARK_E [CHAR (4)]
KDKG1 [CHAR (2)]
KDKG2 [CHAR (2)]
KDKG3 [CHAR (2)]
KDKG4 [CHAR (2)]
KDKG5 [CHAR (2)]
WKWAE [CUKY (5)]
AKWAE [CUKY (5)]
J_1AINDXP [CHAR (5)]
DELCO [CHAR (3)]
FFPRF [CHAR (8)]
BEMOT [CHAR (2)]
PROLI [CHAR (3)]
VSART [CHAR (2)]
TRATY [CHAR (4)]
SDABW [CHAR (18)]
WMINR [CHAR (10)]