

SAP ABAP table MASSQUOTVBAP {Generated Table for View}

MASSQUOTVBAP-AUFNR = AUFK-AUFNR

AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

0..N

MASSQUOTVBAP-FERC_IND = FERC_C7-IND

FERC_C7
MANDT [CLNT (3)]
IND [CHAR (4)]

0..N

MASSQUOTVBAP-J_1BCFOP = J_1BAG-CFOP

J_1BAG
MANDT [CLNT (3)]
CFOP [CHAR (10)]

0..N

MASSQUOTVBAP-J_1BTAXLW1 = J_1BATL1-TAXLAW

J_1BATL1
MANDT [CLNT (3)]
TAXLAW [CHAR (3)]

0..N

MASSQUOTVBAP-J_1BTAXLW2 = J_1BATL2-TAXLAW

J_1BATL2
MANDT [CLNT (3)]
TAXLAW [CHAR (3)]

0..N

MASSQUOTVBAP-J_1BTAXLW3 = J_1BATL3-TAXLAW

J_1BATL3
MANDT [CLNT (3)]
TAXLAW [CHAR (3)]

0..N

MASSQUOTVBAP-J_1BTAXLW4 = J_1BATL4A-TAXLAW

J_1BATL4A
MANDT [CLNT (3)]
TAXLAW [CHAR (3)]

0..N

MASSQUOTVBAP-J_1BTAXLW5 = J_1BATL5-TAXLAW

J_1BATL5
MANDT [CLNT (3)]
TAXLAW [CHAR (3)]

0..N

MASSQUOTVBAP-J_1BTXSDC = J_1BTXSDC-TAXCODE

J_1BTXSDC
MANDT [CLNT (3)]
TAXCODE [CHAR (2)]

0..N

MASSQUOTVBAP-CLINT = KLAH-CLINT

KLAH
MANDT [CLNT (3)]
CLINT [NUMC (10)]

0..N

MASSQUOTVBAP-KNUMA_AG = KONA-KNUMA

KONA
MANDT [CLNT (3)]
KNUMA [CHAR (10)]

0..N

MASSQUOTVBAP-KNUMA_PI = KONA-KNUMA

0..N

MASSQUOTVBAP-MATNR = MARA-MATNR

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

0..N

MASSQUOTVBAP-MATWA = MARA-MATNR

0..N

MASSQUOTVBAP-PMATN = MARA-MATNR

MCHA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
CHARG [CHAR (10)]

0..N

MASSQUOTVBAP-VPMAT = MARA-MATNR

0..N

MASSQUOTVBAP-CHARG = MCHA-CHARG

0..N

MASSQUOTVBAP-MSR_RET_REASON = MSR_C_RET_REASON-RET_REASON

MSR_C_RET_REASON
MANDT [CLNT (3)]
RET_REASON [CHAR (3)]

0..N

MASSQUOTVBAP-MSR_REFUND_CODE = MSR_C_RET_REFUND-RETURNS_REFUND

0..N

MSR_C_RET_REFUND
MANDT [CLNT (3)]
RETURNS_REFUND [CHAR (3)]

MASSQUOTVBAP-OBJNR = ONR00-OBJNR

0..N

ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]

MASSQUOTVBAP-PS_PSP_PNR = PRPS-PSPNR

0..N

PRPS
MANDT [CLNT (3)]
PSPNR [NUMC (8)]

MASSQUOTVBAP-SERNR = SNUM-SERNR

0..N

SNUM
MANDT [CLNT (3)]
SERNR [CHAR (8)]

MASSQUOTVBAP-MANDT = T000-MANDT

0..N

T000
MANDT [CLNT (3)]

MASSQUOTVBAP-LGORT = T001L-LGORT

0..N

T001L
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LGORT [CHAR (4)]

MASSQUOTVBAP-VPWRK = T001W-WERKS

0..N

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

MASSQUOTVBAP-GEWEI = T006-MSEHI

0..N

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

MASSQUOTVBAP-KMEIN = T006-MSEHI

0..N

MASSQUOTVBAP-MEINS = T006-MSEHI

0..N

MASSQUOTVBAP-PRBME = T006-MSEHI

0..N

MASSQUOTVBAP-VOLEH = T006-MSEHI

0..N

T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]

MASSQUOTVBAP-VRKME = T006-MSEHI

0..N

T148
MANDT [CLNT (3)]
SOBKZ [CHAR (1)]

MASSQUOTVBAP-ZIEME = T006-MSEHI

0..N

T149D
MANDT [CLNT (3)]
BWTAR [CHAR (10)]

MASSQUOTVBAP-SOBKZ = T148-SOBKZ

0..N

T163K
MANDT [CLNT (3)]
KNTTP [CHAR (1)]

MASSQUOTVBAP-KONTDP = T178-KONTDP

0..N

T178
MANDT [CLNT (3)]
KONTDP [CHAR (2)]

MASSQUOTVBAP-UKONM = T178-KONTDP

0..N

T179
MANDT [CLNT (3)]
PRODH [CHAR (18)]

MASSQUOTVBAP-PRODH = T179-PRODH

0..N

T190S
MANDT [CLNT (3)]
KOSCH [CHAR (18)]

MASSQUOTVBAP-KOSCH = T190S-KOSCH

0..N

MASSQUOTVBAP-SERAIL = T377P-SERAIL

0..N

T377P
MANDT [CLNT (3)]
SERAIL [CHAR (4)]

MASSQUOTVBAP-BEDAE = T459A-BEDAE

0..N

T459A
MANDT [CLNT (3)]
BEDAE [CHAR (4)]

MASSQUOTVBAP-EXART = T605-EXART

0..N

T605
MANDT [CLNT (3)]
LANDI [CHAR (3)]
EXART [CHAR (2)]

MASSQUOTVBAP-KALSM_K = T683-KALSM

0..N

T683
MANDT [CLNT (3)]
KVEWE [CHAR (1)]
KAPPL [CHAR (2)]
KALSM [CHAR (6)]

MASSQUOTVBAP-ABFOR = T691K-ABSFO

0..N

T691K
MANDT [CLNT (3)]
ABSFO [CHAR (2)]

MASSQUOTVBAP-KALVAR = TCK03-KLVAR

0..N

TCK03
MANDT [CLNT (3)]
KLVAR [CHAR (4)]

MASSQUOTVBAP-WAERC = TCURC-WAERS

0..N

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

MASSQUOTVBAP-GSBER = TGSB-GSBER

0..N

TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]

MASSQUOTVBAP-ABGRS = TKKAA-ABGSL

0..N

TKKAA
MANDT [CLNT (3)]
ABGSL [CHAR (6)]

MASSQUOTVBAP-MFRGR = TMFG-MFRGR

0..N

TMFG
MANDT [CLNT (3)]
MFRGR [CHAR (8)]

MASSQUOTVBAP-MTVFP = TMVF-MTVFP

0..N

TMVF
MANDT [CLNT (3)]
MTVFP [CHAR (2)]

MASSQUOTVBAP-LPRIO = TPRI0-LPRIO

0..N

TPRIO
MANDT [CLNT (3)]
LPRIO [NUMC (2)]

MASSQUOTVBAP-SPART = TSPA-SPART

0..N

TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]

MASSQUOTVBAP-ABGRU = TVAG-ABGRU

0..N

TVAG
MANDT [CLNT (3)]
ABGRU [CHAR (2)]

MASSQUOTVBAP-BONUS = TVBO-BONUS

0..N

TVBO
MANDT [CLNT (3)]
BONUS [CHAR (2)]

MASSQUOTVBAP-MAGR V = TVEGR-MAGR V

0..N

TVEGR
MANDT [CLNT (3)]
MAGR V [CHAR (4)]

MASSQUOTVBAP-FAKSP = TVFS-FAKSP

0..N

TVFS
MANDT [CLNT (3)]
FAKSP [CHAR (2)]

MASSQUOTVBAP-KTGRM = TVKM-KTGRM

0..N

TVKM
MANDT [CLNT (3)]
KTGRM [CHAR (2)]

MASSQUOTVBAP-VKAUS = TVLV-ABRWV

0..N

TVLV
MANDT [CLNT (3)]
ABRWV [CHAR (3)]

MASSQUOTVBAP-MVGR1 = TVM1-MVGR1

0..N

TVM1
MANDT [CLNT (3)]
MVGR1 [CHAR (3)]

MASSQUOTVBAP-MVGR2 = TVM2-MVGR2

0..N

TVM2
MANDT [CLNT (3)]
MVGR2 [CHAR (3)]

MASSQUOTVBAP-MVGR3 = TVM3-MVGR3

0..N

TVM3
MANDT [CLNT (3)]
MVGR3 [CHAR (3)]

MASSQUOTVBAP-MVGR4 = TVM4-MVGR4

0..N

TVM4
MANDT [CLNT (3)]
MVGR4 [CHAR (3)]

MASSQUOTVBAP-MVGR5 = TVM5-MVGR5

0..N

TVM5
MANDT [CLNT (3)]
MVGR5 [CHAR (3)]

MASSQUOTVBAP-PROVG = TVPR-PROVG

0..N

TVPR
MANDT [CLNT (3)]
PROVG [CHAR (2)]

MASSQUOTVBAP-PSTYV = TVPT-PSTYV

0..N

TVPT
MANDT [CLNT (3)]
PSTYV [CHAR (4)]

MASSQUOTVBAP-VKGRU = TVRMAVK-VORGA

0..N

TVRMAVK
MANDT [CLNT (3)]
VORGA [CHAR (3)]

MASSQUOTVBAP-ROUTE = TVRO-ROUTE

0..N

TVRO
MANDT [CLNT (3)]
ROUTE [CHAR (6)]

MASSQUOTVBAP-VSTEL = TVST-VSTEL

0..N

TVST
MANDT [CLNT (3)]
VSTEL [CHAR (4)]

MASSQUOTVBAP-SUGRD = TVSU-SUGRD

0..N

TVSU
MANDT [CLNT (3)]
SUGRD [CHAR (4)]

MASSQUOTVBAP-VBELN = VBUK-VBELN

0..N

TVZP
MANDT [CLNT (3)]
PLAVO [CHAR (4)]

MASSQUOTVBAP-VBELV = VBUK-VBELN

0..N

VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]

MASSQUOTVBAP-POSNR = VBUP-POSNR

0..N

VBUP
MANDT [CLNT (3)]
POSNR [NUMC (6)]

MASSQUOTVBAP-VGPOS = VBUP-POSNR

0..N

MASSQUOTVBAP-WKTPS = VBUP-POSNR

0..N

WSOH
MANDT [CLNT (3)]
SKOPF [CHAR (18)]

0..N

MASSQUOTVBAP
MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]
MATNR [CHAR (18)]
MATWA [CHAR (18)]
PMATN [CHAR (18)]
CHARG [CHAR (10)]
MATKL [CHAR (9)]
PSTYV [CHAR (4)]
ABGRU [CHAR (2)]
PRODH [CHAR (18)]
ZIEME [UNIT (3)]
MEINS [UNIT (3)]
VKGRU [CHAR (3)]
VKAUS [CHAR (3)]
FAKSP [CHAR (2)]
SPART [CHAR (2)]
GSBER [CHAR (4)]
WAERK [CUKY (5)]
VRKME [UNIT (3)]
GEWEI [UNIT (3)]
VOLEH [UNIT (3)]
VBELV [CHAR (10)]
POSNV [NUMC (6)]
VBEL [CHAR (10)]
VGPOS [NUMC (6)]
LPRI0 [NUMC (2)]
LGORT [CHAR (4)]
VSTEL [CHAR (4)]
ROUTE [CHAR (6)]
KMEIN [UNIT (3)]
MTVFP [CHAR (2)]
KONTDP [CHAR (2)]
KTGRM [CHAR (2)]
BONUS [CHAR (2)]
PROVG [CHAR (2)]
BWTAR [CHAR (10)]
MVGR1 [CHAR (3)]
MVGR2 [CHAR (3)]
MVGR3 [CHAR (3)]
MVGR4 [CHAR (3)]
MVGR5 [CHAR (3)]
SUGRD [CHAR (4)]
SOBKZ [CHAR (1)]
PS_PSP_PNR [NUMC (8)]
AUFNR [CHAR (12)]
VPMAT [CHAR (18)]
VPWRK [CHAR (4)]
PRBME [UNIT (3)]
KNTTP [CHAR (1)]
SERNR [CHAR (8)]
OBJNR [CHAR (22)]
ABGRS [CHAR (6)]
BEDAE [CHAR (4)]
SERAIL [CHAR (4)]
MAGR V [CHAR (4)]
EXART [CHAR (2)]
CLINT [NUMC (10)]
KALSM_K [CHAR (6)]
KALVAR [CHAR (4)]
KOSCH [CHAR (18)]
UPMAT [CHAR (18)]
UKONM [CHAR (2)]
MFRGR [CHAR (8)]
PLAVO [CHAR (4)]</