

SAP ABAP table MMPUR_PRINT_KOMK {Print structure for KOMK}

The diagram illustrates the mapping of data fields from a source system to a target system. The fields are organized into three main columns: a left column with field names and their data types, a middle column with mapping rules, and a right column with the target field names and their data types. Dashed lines connect the fields to their corresponding mapping rules and then to the target fields. The fields are color-coded: red for mandatory, green for optional, and blue for optional with a default value. The mapping rules are color-coded: green for mandatory, yellow for optional, and blue for optional with a default value. The target fields are color-coded: green for mandatory, yellow for optional, and blue for optional with a default value.

Left Column (Source Fields):

- J_1ADTYP** (MANDT [CLNT (3)])
- J_1AFITP** (MANDT [CLNT (3)], KOART [CHAR (1)], J_1AFITP [CHAR (2)])
- J_1AGICD** (MANDT [CLNT (3)], LANDI [CHAR (3)], J_1AGICD [CHAR (2)])
- J_1AINFT20** (MANDT [CLNT (3)], J_1AINDX [CHAR (5)])
- J_1ARFZ** (MANDT [CLNT (3)], J_1ARFZ [CHAR (1)])
- J_1ATXREL** (MANDT [CLNT (3)], J_1ATXREL [CHAR (10)])
- J_1BTCNAE** (MANDT [CLNT (3)], J_1BTCNAE [CHAR (7)])
- J_1BTCMSIZE** (MANDT [CLNT (3)], J_1BTCMSIZE [CHAR (2)])
- J_1BTDECREGPC** (MANDT [CLNT (3)], J_1BTDECREGPC [CHAR (2)])
- J_1BTICMSTAXPAY** (MANDT [CLNT (3)], J_1BTICMSTAXPAY [CHAR (2)])
- J_1BTINDTYP** (MANDT [CLNT (3)], J_1BTINDTYP [CHAR (2)])
- J_1BTLEGALNAT** (MANDT [CLNT (3)], J_1BTLEGALNAT [NUMC (4)])
- J_1BTDDT** (MANDT [CLNT (3)], J_1BTDDT [CHAR (2)])
- KNA1** (MANDT [CLNT (3)], KUNNR [CHAR (10)])
- KONA** (MANDT [CLNT (3)], KNUMA [CHAR (10)])
- KONBBYH** (MANDT [CLNT (3)], BBYNR [CHAR (12)])
- LFA1** (MANDT [CLNT (3)], LIFNR [CHAR (10)])
- T000** (MANDT [CLNT (3)])
- T001** (MANDT [CLNT (3)], BUKRS [CHAR (4)])
- T001W** (MANDT [CLNT (3)], WERKS [CHAR (4)])
- T0030** (CLIENT [CLNT (3)], AUART [CHAR (4)])
- T005** (MANDT [CLNT (3)], LAND1 [CHAR (3)])
- T005E** (MANDT [CLNT (3)], LAND1 [CHAR (3)], REGIO [CHAR (3)], COUNC [CHAR (3)])
- T005G** (MANDT [CLNT (3)], LAND1 [CHAR (3)], REGIO [CHAR (3)], CITYC [CHAR (4)])
- T005S** (MANDT [CLNT (3)], LAND1 [CHAR (3)], BLAND [CHAR (3)])
- T016** (MANDT [CLNT (3)], BRSCH [CHAR (4)])
- T024E** (MANDT [CLNT (3)], EKORG [CHAR (4)])
- T151** (MANDT [CLNT (3)], KDGRP [CHAR (2)])
- T171** (MANDT [CLNT (3)], BZIRK [CHAR (6)])
- T173** (MANDT [CLNT (3)], VSART [CHAR (2)])
- T188** (MANDT [CLNT (3)], KONDA [CHAR (2)])
- T189** (MANDT [CLNT (3)], PLTYP [CHAR (2)])
- T681A** (KAPPL [CHAR (2)])
- T683** (MANDT [CLNT (3)], KVEWE [CHAR (1)], KAPPL [CHAR (2)], KALSM [CHAR (6)])
- TCURC** (MANDT [CLNT (3)], WAERS [CUKY (5)])
- TCURV** (MANDT [CLNT (3)], KURST [CHAR (4)])
- TGSB** (MANDT [CLNT (3)], GSBER [CHAR (4)])
- TINC** (MANDT [CLNT (3)], INCO1 [CHAR (3)])
- TKA01** (MANDT [CLNT (3)], KOKRS [CHAR (4)])
- TKA05** (MANDT [CLNT (3)], KOSAR [CHAR (1)])
- TKEB** (MANDT [CLNT (3)], ERKRS [CHAR (4)])
- TKVS** (MANDT [CLNT (3)], VERSI [CHAR (3)])
- TSPA** (MANDT [CLNT (3)], SPART [CHAR (2)])
- TTDS** (MANDT [CLNT (3)], TPLST [CHAR (4)])
- TTXJ** (MANDT [CLNT (3)], KALSM [CHAR (6)], TXJCD [CHAR (15)])
- TVBUR** (MANDT [CLNT (3)], VKBUR [CHAR (4)])
- TVFK** (MANDT [CLNT (3)], FKART [CHAR (4)])
- TVFTZ** (MANDT [CLNT (3)], TRFZN [CHAR (10)])
- TVGA** (MANDT [CLNT (3)], VRGAR [CHAR (1)])
- TVKGR** (MANDT [CLNT (3)], VKGRP [CHAR (3)])
- TVKN** (MANDT [CLNT (3)], KNOTE [CHAR (10)])
- TVKO** (MANDT [CLNT (3)], VKORG [CHAR (4)])
- TVRO** (MANDT [CLNT (3)], ROUTE [CHAR (6)])
- TVSAK** (MANDT [CLNT (3)], SDABW [CHAR (4)])
- TVSB** (MANDT [CLNT (3)], VSBED [CHAR (2)])
- TVST** (MANDT [CLNT (3)], VSTEL [CHAR (4)])
- TVTK** (MANDT [CLNT (3)], SHTYP [CHAR (4)])
- TVTW** (MANDT [CLNT (3)], VTWEG [CHAR (2)])
- TZONE** (MANDT [CLNT (3)], LAND1 [CHAR (3)], ZONE1 [CHAR (10)])
- VBUK** (MANDT [CLNT (3)], VBELN [CHAR (10)])
- VTADD01** (MANDT [CLNT (3)], ADD_INFO [CHAR (10)])
- VTADD02** (MANDT [CLNT (3)], ADD_INFO [CHAR (10)])
- VTADD03** (MANDT [CLNT (3)], ADD_INFO [CHAR (10)])
- VTADD04** (MANDT [CLNT (3)])

Middle Column (Mapping Rules):

- MMPUR_PRINT_KOMK-J_1ADTYP = J_1ADTYP-J_1ADTYP
- MMPUR_PRINT_KOMK-J_1AFITP = J_1AFITP-J_1AFITP
- MMPUR_PRINT_KOMK-J_1AGICD = J_1AGICD-J_1AGICD
- MMPUR_PRINT_KOMK-J_1AINDX = J_1AINFT20-J_1AINDX
- MMPUR_PRINT_KOMK-J_1ARFZ = J_1ARFZ-J_1ARFZ
- MMPUR_PRINT_KOMK-J_1ATXREL = J_1ATXREL-J_1ATXREL
- MMPUR_PRINT_KOMK-CNAE = J_1BTCNAE-J_1BTCNAE
- MMPUR_PRINT_KOMK-COMSIZE = J_1BTCMSIZE-J_1BTCMSIZE
- MMPUR_PRINT_KOMK-DECREGPC = J_1BTDECREGPC-J_1BTDECREGPC
- MMPUR_PRINT_KOMK-ICMSTAXPAY = J_1BTICMSTAXPAY-J_1BTICMSTAXPAY
- MMPUR_PRINT_KOMK-INDTYP = J_1BTINDTYP-J_1BTINDTYP
- MMPUR_PRINT_KOMK-LEGALNAT = J_1BTLEGALNAT-J_1BTLEGALNAT
- MMPUR_PRINT_KOMK-TDT = J_1BTDDT-J_1BTDDT
- MMPUR_PRINT_KOMK-HIEZU01 = KNA1-KUNNR
- MMPUR_PRINT_KOMK-HIEZU02 = KNA1-KUNNR
- MMPUR_PRINT_KOMK-HIEZU03 = KNA1-KUNNR
- MMPUR_PRINT_KOMK-HIEZU04 = KNA1-KUNNR
- MMPUR_PRINT_KOMK-HIEZU05 = KNA1-KUNNR
- MMPUR_PRINT_KOMK-HIEZU06 = KNA1-KUNNR
- MMPUR_PRINT_KOMK-HIEZU07 = KNA1-KUNNR
- MMPUR_PRINT_KOMK-HIEZU08 = KNA1-KUNNR
- MMPUR_PRINT_KOMK-HIEZU09 = KNA1-KUNNR
- MMPUR_PRINT_KOMK-HIEZU10 = KNA1-KUNNR
- MMPUR_PRINT_KOMK-KNRZE = KNA1-KUNNR
- MMPUR_PRINT_KOMK-KUNNR = KNA1-KUNNR
- MMPUR_PRINT_KOMK-KUNRE = KNA1-KUNNR
- MMPUR_PRINT_KOMK-KUNWE = KNA1-KUNNR
- MMPUR_PRINT_KOMK-KNUMA = KONA-KNUMA
- MMPUR_PRINT_KOMK-BBYNR = KONBBYH-BBYNR
- MMPUR_PRINT_KOMK-LIFNR = LFA1-LIFNR
- MMPUR_PRINT_KOMK-LIFRE = LFA1-LIFNR
- MMPUR_PRINT_KOMK-SPDNR = LFA1-LIFNR
- MMPUR_PRINT_KOMK-TDLNR = LFA1-LIFNR
- MMPUR_PRINT_KOMK-TDLNR_FA = LFA1-LIFNR
- MMPUR_PRINT_KOMK-MANDT = T000-MANDT
- MMPUR_PRINT_KOMK-BUKRS = T001-BUKRS
- MMPUR_PRINT_KOMK-WERKV = T001W-WERKS
- MMPUR_PRINT_KOMK-AUART = T0030-AUART
- MMPUR_PRINT_KOMK-ALAND = T005-LAND1
- MMPUR_PRINT_KOMK-LAND1 = T005E-LAND1
- MMPUR_PRINT_KOMK-LAND1A = T005E-LAND1
- MMPUR_PRINT_KOMK-LAND1Z = T005E-LAND1
- MMPUR_PRINT_KOMK-SLAND1_A = T005E-LAND1
- MMPUR_PRINT_KOMK-SLAND1_Z = T005E-LAND1
- MMPUR_PRINT_KOMK-TDLNR_LND = T005E-LAND1
- MMPUR_PRINT_KOMK-COUNC = T005E-COUNC
- MMPUR_PRINT_KOMK-CITYC = T005G-CITYC
- MMPUR_PRINT_KOMK-J_1AREGIO = T005S-BLAND
- MMPUR_PRINT_KOMK-REGIO = T005S-BLAND
- MMPUR_PRINT_KOMK-REGIOA = T005S-BLAND
- MMPUR_PRINT_KOMK-REGIOZ = T005S-BLAND
- MMPUR_PRINT_KOMK-WKREG = T005S-BLAND
- MMPUR_PRINT_KOMK-BRSCH = T016-BRSCH
- MMPUR_PRINT_KOMK-EKORG = T024E-EKORG
- MMPUR_PRINT_KOMK-KDGRP = T151-KDGRP
- MMPUR_PRINT_KOMK-BZIRK = T171-BZIRK
- MMPUR_PRINT_KOMK-VSART = T173-VSART
- MMPUR_PRINT_KOMK-KONDA = T188-KONDA
- MMPUR_PRINT_KOMK-PLTYP = T189-PLTYP
- MMPUR_PRINT_KOMK-KAPPL = T681A-KAPPL
- MMPUR_PRINT_KOMK-KALSM = T683-KALSM
- MMPUR_PRINT_KOMK-HWAER = TCURC-WAERS
- MMPUR_PRINT_KOMK-WAERK = TCURC-WAERS
- MMPUR_PRINT_KOMK-KURST = TCURV-KURST
- MMPUR_PRINT_KOMK-GSBER = TGSB-GSBER
- MMPUR_PRINT_KOMK-INCO1 = TINC-INCO1