

SAP ABAP table MSAM_MO_NOTIFICATION_LIST {Notification List}

MSAM_MO_NOTIFICATION_LIST-SUB_NUMBER = ANLA-ANLN2

ANLA
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]
<u>ANLN1</u> [CHAR (12)]
<u>ANLN2</u> [CHAR (4)]

MSAM_MO_NOTIFICATION_LIST-ASSET_NO = ANLH-ANLN1

ANLH
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]
<u>ANLN1</u> [CHAR (12)]

MSAM_MO_NOTIFICATION_LIST-ORDERID = AUFK-AUFNR

AUFK
<u>MANDT</u> [CLNT (3)]
<u>AUFNR</u> [CHAR (12)]

MSAM_MO_NOTIFICATION_LIST-STDGORD = AUFK-AUFNR

CRID
<u>MANDT</u> [CLNT (3)]
<u>OBJTY</u> [CHAR (2)]
<u>OBJID</u> [NUMC (8)]

MSAM_MO_NOTIFICATION_LIST-STLMTORDER = AUFK-AUFNR

MSAM_MO_NOTIFICATION_LIST-PM_WKCTR = CRID-OBJID

MSAM_MO_NOTIFICATION_LIST-PP_WKCTR = CRID-OBJID

MSAM_MO_NOTIFICATION_LIST-COSTCENTER = CSKS-KOSTL

CSKS
<u>MANDT</u> [CLNT (3)]
<u>KOKRS</u> [CHAR (4)]
<u>KOSTL</u> [CHAR (10)]
<u>DATBI</u> [DATS (8)]

MSAM_MO_NOTIFICATION_LIST-EQUIPMENT = EQUI-EQUNR

EQUI
<u>MANDT</u> [CLNT (3)]
<u>EQUNR</u> [CHAR (18)]

MSAM_MO_NOTIFICATION_LIST-CUST_NO = KNA1-KUNNR

KNA1
<u>MANDT</u> [CLNT (3)]
<u>KUNNR</u> [CHAR (10)]

MSAM_MO_NOTIFICATION_LIST-ASSEMBLY = MARA-MATNR

MSAM_MO_NOTIFICATION_LIST-MATERIAL = MARA-MATNR

MARA
<u>MANDT</u> [CLNT (3)]
<u>MATNR</u> [CHAR (18)]

MSAM_MO_NOTIFICATION_LIST-MNTPLAN = MPLA-WARPL

MPLA
<u>MANDT</u> [CLNT (3)]
<u>WARPL</u> [CHAR (12)]

MSAM_MO_NOTIFICATION_LIST-MAINTITEM = MPOS-WAPOS

MPOS
<u>MANDT</u> [CLNT (3)]
<u>WAPOS</u> [CHAR (16)]

MSAM_MO_NOTIFICATION_LIST-OBJECT NO = ONR00-OBJNR

ONR00
<u>MANDT</u> [CLNT (3)]
<u>OBJNR</u> [CHAR (22)]

MSAM_MO_NOTIFICATION_LIST-CODING = QPCD-CODE

QPCD
<u>MANDT</u> [CLNT (3)]
<u>KATALOGART</u> [CHAR (2)]
<u>CODEGRUPPE</u> [CHAR (8)]
<u>CODE</u> [CHAR (4)]

MSAM_MO_NOTIFICATION_LIST-CODE_GROUP = QPGR-CODEGRUPPE

QPGR
<u>MANDT</u> [CLNT (3)]
<u>KATALOGART</u> [CHAR (2)]
<u>CODEGRUPPE</u> [CHAR (8)]

MSAM_MO_NOTIFICATION_LIST-COMP CODE = T001-BUKRS

T001
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]

MSAM_MO_NOTIFICATION_LIST-MAINTPLANT = T001W-WERKS

T001W
<u>MANDT</u> [CLNT (3)]
<u>WERKS</u> [CHAR (4)]

MSAM_MO_NOTIFICATION_LIST-UNIT = T006-MSEHI

T006
<u>MANDT</u> [CLNT (3)]
<u>MSEHI</u> [UNIT (3)]

MSAM_MO_NOTIFICATION_LIST-PLANGROUP = T024I-INGRP

T024I
<u>MANDT</u> [CLNT (3)]
<u>IWERK</u> [CHAR (4)]
<u>INGRP</u> [CHAR (3)]

MSAM_MO_NOTIFICATION_LIST-CATPROFILE = T352B-RBNR

T352B
<u>MANDT</u> [CLNT (3)]
<u>RBNR</u> [CHAR (9)]

MSAM_MO_NOTIFICATION_LIST-PRIORITY = T356-PRIOK

MSAM_MO_NOTIFICATION_LIST-PRIOTYPE = T356A-ARTPR

T356
<u>MANDT</u> [CLNT (3)]
<u>ARTPR</u> [CHAR (2)]
<u>PRIOK</u> [CHAR (1)]

MSAM_MO_NOTIFICATION_LIST-PLSECTN = T357-BEBER

T356A
<u>MANDT</u> [CLNT (3)]
<u>ARTPR</u> [CHAR (2)]

T357
<u>MANDT</u> [CLNT (3)]
<u>WERKS</u> [CHAR (4)]
<u>BEBER</u> [CHAR (3)]

MSAM_MO_NOTIFICATION_LIST-ABCINDIC = T370C-ABCKZ

T370C
<u>MANDT</u> [CLNT (3)]
<u>ABCKZ</u> [CHAR (1)]

MSAM_MO_NOTIFICATION_LIST-PLANPLANT = T399I-IWERK

T399I
<u>MANDT</u> [CLNT (3)]
<u>IWERK</u> [CHAR (4)]

MSAM_MO_NOTIFICATION_LIST-MAINTLOC = T499S-STAND

T499S
<u>MANDT</u> [CLNT (3)]
<u>WERKS</u> [CHAR (4)]
<u>STAND</u> [CHAR (10)]

MSAM_MO_NOTIFICATION_LIST-BUS_AREA = TGSB-GSBER

TGSB
<u>MANDT</u> [CLNT (3)]
<u>GSBER</u> [CHAR (4)]

MSAM_MO_NOTIFICATION_LIST-CO_AREA = TKA01-KOKRS

TKA01
<u>MANDT</u> [CLNT (3)]
<u>KOKRS</u> [CHAR (4)]

MSAM_MO_NOTIFICATION_LIST-CAT_TYPE = TQ15-KATALOGART

TQ15
<u>MANDT</u> [CLNT (3)]
<u>KATALOGART</u> [CHAR (2)]

MSAM_MO_NOTIFICATION_LIST-NOTIF_TYPE = TQ80-QMART

TQ80
<u>MANDT</u> [CLNT (3)]
<u>QMART</u> [CHAR (2)]

MSAM_MO_NOTIFICATION_LIST-DIVISION = TSPA-SPART

MSAM_MO_NOTIFICATION_LIST-DIVISION_LOC_ACC = TSPA-SPART

TSPA
<u>MANDT</u> [CLNT (3)]
<u>SPART</u> [CHAR (2)]

MSAM_MO_NOTIFICATION_LIST-NOTIFTMEZ = TTZZ-TZONE

TTZZ
<u>CLIENT</u> [CLNT (3)]
<u>TZONE</u> [CHAR (6)]

MSAM_MO_NOTIFICATION_LIST-SALES_OFFICE = TVBUR-VKBUR

TVBUR
<u>MANDT</u> [CLNT (3)]
<u>VKBUR</u> [CHAR (4)]

MSAM_MO_NOTIFICATION_LIST-SALES_GRP = TVKGR-VKGRP

MSAM_MO_NOTIFICATION_LIST-SALES_ORG = TVKO-VKORG

TVKGR
<u>MANDT</u> [CLNT (3)]
<u>VKGRP</u> [CHAR (3)]

MSAM_MO_NOTIFICATION_LIST-SALES_ORG_LOC_ACC = TVKO-VKORG

MSAM_MO_NOTIFICATION_LIST-DISTR_CHAN = TVTW-VTWEG

TVKO
<u>MANDT</u> [CLNT (3)]
<u>VKORG</u> [CHAR (4)]

MSAM_MO_NOTIFICATION_LIST-DIST_CHAN_LOC_ACC = TVTW-VTWEG

MSAM_MO_NOTIFICATION_LIST-DOC_NUMBER = VBUK-VBELN

TVTW
<u>MANDT</u> [CLNT (3)]
<u>VTWEG</u> [CHAR (2)]

MSAM_MO_NOTIFICATION_LIST-SALES_ORD = VBUK-VBELN

VBUK
<u>MANDT</u> [CLNT (3)]
<u>VBELN</u> [CHAR (10)]

MSAM_MO_NOTIFICATION_LIST-ITM_NUMBER = VBUP-POSNR

VBUP
<u>MANDT</u> [CLNT (3)]
<u>VBELN</u> [CHAR (10)]
<u>POSNR</u> [NUMC (6)]

MSAM_MO_NOTIFICATION_LIST
<u>NOTIF_TYPE</u> [CHAR (2)]
<u>PLANPLANT</u> [CHAR (4)]
<u>PLANGROUP</u> [CHAR (3)]
<u>PM_WKCTR</u> [NUMC (8)]
<u>EQUIPMENT</u> [CHAR (18)]
<u>ASSEMBLY</u> [CHAR (18)]
<u>MATERIAL</u> [CHAR (18)]
<u>UNIT</u> [UNIT (3)]
<u>MNTPLAN</u> [CHAR (12)]
<u>MAINTITEM</u> [CHAR (16)]
<u>PRIOTYPE</u> [CHAR (2)]
<u>PRIORITY</u> [CHAR (1)]
<u>ORDERID</u> [CHAR (12)]
<u>CUST_NO</u> [CHAR (10)]
<u>OBJECT_NO</u> [CHAR (22)]
<u>SALES_ORD</u> [CHAR (10)]
<u>DIVISION</u> [CHAR (2)]
<u>SALES_ORG</u> [CHAR (4)]
<u>DISTR_CHAN</u> [CHAR (2)]
<u>CATPROFILE</u> [CHAR (9)]
<u>CAT_TYPE</u> [CHAR (1)]
<u>CODE_GROUP</u> [CHAR (8)]
<u>CODING</u> [CHAR (4)]
<u>SALES_OFFICE</u> [CHAR (4)]
<u>SALES_GRP</u> [CHAR (3)]
<u>NOTIFTMEZ</u> [CHAR (6)]
<u>ABCINDIC</u> [CHAR (1)]
<u>MAINTPLANT</u> [CHAR (4)]
<u>MAINTLOC</u> [CHAR (10)]
<u>PLSECTN</u> [CHAR (3)]
<u>PP_WKCTR</u> [NUMC (8)]
<u>BUS_AREA</u> [CHAR (4)]
<u>CO_AREA</u> [CHAR (4)]
<u>COSTCENTER</u> [CHAR (10)]
<u>ASSET_NO</u> [CHAR (12)]
<u>SUB_NUMBER</u> [CHAR (4)]
<u>STDGORD</u> [CHAR (12)]
<u>STLMTORDER</u> [CHAR (12)]
<u>COMP_CODE</u> [CHAR (4)]
<u>SALES_ORG_LOC_ACC</u> [CHAR (4)]
<u>DIVISION_LOC_ACC</u> [CHAR (2)]
<u>DIST_CHAN_LOC_ACC</u> [CHAR (2)]
<u>DOC_NUMBER</u> [CHAR (10)]
<u>ITM_NUMBER</u> [NUMC (6)]